Tanium Integrations Gallery User Guide

2026H2 Semiannual Release

Version 1.7.478

November 19, 2026



The information in this document is subject to change without notice. Further, the information provided in this document is provided "as is" and is believed to be accurate, but is presented without any warranty of any kind, express or implied, except as provided in Tanium's customer sales terms and conditions. Unless so otherwise provided, Tanium assumes no liability whatsoever, and in no event shall Tanium or its suppliers be liable for any indirect, special, consequential, or incidental damages, including without limitation, lost profits or loss or damage to data arising out of the use or inability to use this document, even if Tanium Inc. has been advised of the possibility of such damages.

Any IP addresses used in this document are not intended to be actual addresses. Any examples, command display output, network topology diagrams, and other figures included in this document are shown for illustrative purposes only. Any use of actual IP addresses in illustrative content is unintentional and coincidental.

Please visit https://help.tanium.com for the most current Tanium product documentation.

This documentation may provide access to or information about content, products (including hardware and software), and servicesprovided by third parties ("Third Party Items"). With respect to such Third Party Items, Tanium Inc. and its affiliates (i) are not responsible for such items, and expressly disclaim all warranties and liability of any kind related to such Third Party Items and (ii) will not be responsible for any loss, costs, or damages incurred due to your access to or use of such Third Party Items unless expressly set forth otherwise in an applicable agreement between you and Tanium.

Further, this documentation does not require or contemplate the use of or combination with Tanium products with any particular Third Party Items and neither Tanium nor its affiliates shall have any responsibility for any infringement of intellectual property rights caused by any such combination. You, and not Tanium, are responsible for determining that any combination of Third Party Items with Tanium products is appropriate and will not cause infringement of any third party intellectual property rights.

Tanium is committed to the highest accessibility standards for our products. To date, Tanium has focused on compliance with U.S.Federal regulations - specifically Section 508 of the Rehabilitation Act of 1998. Tanium has conducted 3rd party accessibility assessments over the course of product development for many years. We certify against the WCAG 2.2 / VPAT 2.5 standards for all major product modules. Tanium performs ongoing reassessments as appropriate, given the scope and type of changes to the UI and product features from release to release. In the most recent testing, the Tanium Console UI achieved supports or partially supports for all applicable WCAG 2.2 criteria. Tanium can make available any VPAT reports on a module-by-module basis as part of a larger solution planning process for any customer or prospect.

As new products and features are continuously delivered, Tanium will conduct testing to identify potential gaps in compliance with accessibility guidelines. Tanium is committed to making commercially reasonable efforts to address any gaps as quickly as is feasible, given the severity of the issue and scope of the changes. Tanium factors these objectives into the ongoing delivery schedule of features and releases with our existing resources.

Tanium welcomes customer input on making solutions accessible based on your Tanium modules and assistive technology requirements. Accessibility requirements are important to the Tanium customer community and we are

©2026 Tanium Inc. All Rights Reserved

committed to prioritizing these compliance efforts as part of our overall product roadmap. Tanium maintains transparency on our progress and milestones and welcomes any further questions or discussion around this work. Contact your sales representative, Tanium Support atsupport@tanium.com, or email accessibility@tanium.com to make further inquiries.

Tanium is a trademark of Tanium, Inc. in the U.S. and other countries. Third-party trademarks mentioned are the property of the irrespective owners.

Kubernetes®, K8s®, and the Kubernetes logo are registered trademarks of The Linux Foundation®.

Android, ChromeOS, and Google are trademarks of Google LLC.

iOS, iPad, iPadOS, iPhone, Mac, and macOS are trademarks of Apple Inc., and registered in the U.S. and other countries and regions.

Patents: https://www.tanium.com/patents

Tanium Open Source Disclosure : https://tanium.github.io/opensource/

© 2026 Tanium Inc. All rights reserved.

Table of contents

Overview 14
Benefits of Tanium Integrations Gallery 14
Interoperability with other Tanium products 15

Getting started 16

Requirements 19
Core platform dependencies 19
Solution dependencies 19
Tanium recommended installation 19
Import specific solutions 20
Required dependencies 20
Feature-specific dependencies 20
Tanium™ Module Server 21
Endpoints 21
Host and network security requirements 21
Ports 21
Security exclusions 21
User role requirements 22

Installing 26
Before you begin 26
Import Integrations Gallery with default settings 26
Import Integrations Gallery with custom settings 27
Manage solution dependencies 27
Upgrade Integrations Gallery 27
Verify Integrations Gallery version 28
Troubleshoot issues 28

Configuring 29
Configure Integrations Gallery 29

©2026 Tanium Inc. All Rights Reserved

Link your Account Portal 29
Move your Tanium Account 29
Set up Integrations Gallery users 30

Managing the Microsoft Azure VM Extensions integration 32
Requirements 32
Operating system support in Microsoft Azure 32
Network connectivity 32
Computer group dependencies 32
User role requirements 33
View the Details page 35
View the Configuration page 36
View the Tanium Content page 36
View the Support page 37
View the About page 37
Enable the integration 38
Create a Tanium Client initialization profile 38
Obtain the tanium-init.dat file for deployment 40
Disable the integration 41
Troubleshoot the Azure VM Extensions integration 42
Collect logs 42
Cannot install the Tanium Client VM extension on Microsoft Azure VMs 42

Managing the Microsoft Azure Arc integration 44
Requirements 44
Operating system support on Microsoft Azure Arc 44
Azure Arc prerequisites 44
Network connectivity 45
Computer group dependencies 45
User role requirements 45
Enable the integration 47
Create a Tanium Client initialization profile 48
Obtain the tanium-init.dat file for deployment 49
View the Details page 51
View the Configuration page 51
View the Tanium Content page 52

©2026 Tanium Inc. All Rights Reserved

View the About page 52
Disable the integration 53

Managing the Microsoft Security Copilot integration 54
Getting started with the Microsoft Security Copilot integration 54
Requirements for the Microsoft Security Copilot integration 56
Core platform dependencies 56
Solution dependencies 56
Tanium recommended installation 57
Import a specific solution 57
Required dependencies 57
Feature-specific dependencies 58
Third-party software 59
User role and persona requirements 59
View the Details page 62
View the Configuration page 62
View the About page 63
Configuring the Microsoft Security Copilot integration 63
Allow secure network connections between Tanium and Microsoft Security Copilot 64
Show Microsoft Security Copilot integration configuration 64
Set up Tanium integration with Microsoft Security Copilot users 64
Configure Tanium API Plugin for Microsoft Security Copilot 66
Configure Tanium agents for Microsoft Security Copilot 68
Using the Tanium API plugin for Microsoft Security Copilot 71
Use Tanium skill prompts with Microsoft Security Copilot 71
Tanium Skills example prompts 73
Get Real-time Data from Endpoints prompt sensor support 80
Get Real-time Data from Endpoints supported sensors 81
Using the Tanium Security Health Analyzer Agent 87
Tanium Security Health Analyzer Agent details 87
Submit a prompt to the Tanium Security Health Analyzer Agent 88
Tanium Security Health Analyzer Agent example prompt 88
Using the Tanium Security Triage Agent 89
Tanium Security Triage Agent details 89
Submit a prompt to the Tanium Security Triage Agent 90
Obtain a Threat Response alert GUID 90

©2026 Tanium Inc. All Rights Reserved

Tanium Security Triage Agent example prompt 91
Pass an alert GUID directly to an agent 91
Using the Tanium Security Triage Agent with Identity Insights 92
Tanium Security Triage Agent with Identity Insights details 92
Submit a prompt to the Tanium Security Triage Agent with Identity Insights 92
Obtain a Threat Response alert GUID 92
Tanium Security Triage Agent with Identity Insights example prompt 93
Pass an alert GUID directly to an agent 94
Troubleshooting the Microsoft Security Copilot integration 94
Allow Microsoft Security Copilot egress IP addresses 94
Rotate Microsoft Security Copilot API tokens 95
Review Microsoft Security Copilot-related API token audit logging 95
Review Microsoft Security Copilot-related questions in Tanium 96
Improve selection of Tanium Skills 97

Managing the Microsoft Teams integration with Jump Gate 98
Requirements 98
Core platform dependencies 98
Required dependencies 98
Feature-specific dependencies 99
User role and persona requirements 99
View the Details page 100
View the Configuration page 101
View the About page 101
Configure Microsoft Teams integration with Tanium Jump Gate 102
Enable the Microsoft Teams integration 102
Create a Microsoft Teams configuration 102
Edit a Microsoft Teams instance 103
Delete a Microsoft Teams instance 104
Troubleshoot issues 104
Cannot establish a connection between Tanium and Microsoft Teams 104
The Network Egress Allow List was not updated 104

Managing the ScreenMeet Screen Sharing integration 105
Requirements 105
Managing the ScreenMeet Screen Sharing integration 107

©2026 Tanium Inc. All Rights Reserved

Supported operating systems for ScreenMeet 107
Ports for Screen Sharing communication 108
Network requirements 108
User role requirements 108
View the Details page 113
View the Configuration page 114
View the Tanium Content page 115
View the Support page 115
View the About page 115
Enable the integration 116
Integrate with ServiceNow 116
Configure personas to establish unattended screen sharing sessions 117
Open an endpoint screen sharing session 119
Open a screen sharing session from an endpoint 121
Open a screen sharing session from Direct Connect 122
Open a screen sharing session from Reporting 124
Open a screen sharing session from Performance 125
Open a screen sharing session with an endpoint that does not have a Tanium Client 126
View and join screen sharing sessions 128
Join active sessions in the list of sessions 128
Search for an endpoint to join the active session 128
End an endpoint screen sharing session 128
End active sessions in the list of sessions 129
Search for an endpoint to end the active session 129
Configure ScreenMeet settings 129
Move your Tanium Account 130
Troubleshoot the Screen Sharing integration 130
Collect logs 130
Screen sharing buttons unavailable 131
Contact support 131

Managing the ServiceNow integrations 132
Before you begin 132
Requirements 133
Core platform dependencies 133

©2026 Tanium Inc. All Rights Reserved

Solution dependencies 133
Required dependencies 133
Feature-specific dependencies 134
Third-party software 134
Host and network security requirements 134
Ports 134
Security exclusions 135
User role requirements 135
View the Details page 138
View the Configuration page 139
View the Tanium Content page 139
View the Support page 140
View the About page 140
Configuring the Live UI integration 140
Before you begin with the Live UI integration 140
Live UI user role requirements 141
Enable the Live UI integration 142
Create a ServiceNow instance configuration for Live UI 142
Configuring the SDK for ServiceNow integration 143
Before you begin with the SDK integration 143
SDK user role requirements 143
Enable the SDK integration 144
Create the ServiceNow instance configuration for SDK 145
Configuring the Service Graph Connector for Tanium integration 146
Before you begin with the Service Graph Connector integration 146
Service Graph Connector user role requirements 146
Enable the Service Graph Connector integration 148
Create a ServiceNow instance configuration for Service Graph Connector 148
Configuring the Vulnerability Management integration 150
Before you begin with the Vulnerability Management integration 150
Vulnerability Management user role requirements 150
Enable the Vulnerability Management integration 151
Create a ServiceNow instance for Vulnerability Management 151
Updating ServiceNow instance configuration 153
Edit a ServiceNow instance 153

©2026 Tanium Inc. All Rights Reserved

Delete a ServiceNow instance 154
Troubleshooting ServiceNow integrations 154
Collect logs 154
Cannot establish connection between Tanium and ServiceNow 155
API token is expired 155
Contact Tanium Support 156

Managing the Slack integration with Jump Gate 157
Requirements 157
Core platform dependencies 157
Required dependencies 157
Feature-specific dependencies 158
User role and persona requirements 158
View the Details page 159
View the Configuration page 160
View the About page 160
Configure Slack integration with Tanium Jump Gate 161
Enable the Slack integration 161
Create a Slack configuration 161
Edit a Slack instance 162
Delete a Slack instance 162
Troubleshoot issues 163
Cannot create the Slack app 163
Cannot establish a connection between Tanium and Slack 163
Cannot authorize the connection between Tanium and Slack 163
The Network Egress Allow List was not updated 163

Managing the Tanium Connector for Microsoft Intune 164
Before you begin 164
Entities and endpoints 167
Entity providers 168
Architecture 169
Requirements 170
Core platform dependencies 170
Solution dependencies 171
Required dependencies 171

©2026 Tanium Inc. All Rights Reserved

Feature-specific dependencies 171
Endpoints 172
Supported Internet protocols 172
Supported operating systems 172
Device requirements 172
Third-party software 173
Host and network security requirements 173
Ports 173
Security exclusions 173
User role requirements 174
View the Details page 177
View the Configuration page 178
View the Tanium Content page 178
View the Support page 178
View the About page 179
Configure integration between Tanium and Microsoft Intune 179
Tanium Connector for Microsoft Intune ingestion 180
Interaction between Asset and Tanium Connector for Microsoft Intune 182
Create an Azure client ID and secret 183
(Optional) Include Microsoft Intune devices in Asset views 185
Create a Tanium Connector for Microsoft Intune instance 185
Edit a Tanium Connector for Microsoft Intune instance 187
Delete a Tanium Connector for Microsoft Intune instance 187
Monitor Tanium Connector for Microsoft Intune 188
View Tanium Connector for Microsoft Intune instances 188
Filter Tanium Connector for Microsoft Intune instance list 188
Use Tanium Connector for Microsoft Intune mobile devices and data 189
Issue questions to target Microsoft Intune mobile devices 189
Filter entities by provider in Interact questions 189
Run a remote action on a mobile device 190
Deploy simple actions and ring deployments using Console 191
Deploy actions using an Automate playbook 191
Microsoft Intune remote actions 191
Include Microsoft Intune mobile devices in a report 193
Export Microsoft Intune mobile device data using Tanium Connect 194

©2026 Tanium Inc. All Rights Reserved

Troubleshooting 195
Collect logs 195
Cannot establish connection between Tanium and Microsoft Intune 195
Cannot authenticate to Microsoft Intune 196
Cannot access a route, or retrieve groups or devices, or Microsoft Intune permissions are missing 196
Wipe Device or Retire Device remote actions fail if Multi Admin Approval is enabled 196

Managing the Tanium Security Browser Connector for Microsoft Edge for Business 198
Before you begin 198
Architecture 200
Requirements 200
Core platform dependencies 200
Solution dependencies 201
Required dependencies 201
Feature-specific dependencies 201
Endpoints 202
Supported Internet protocols 202
Supported operating systems 202
Third-party software 202
Host and network security requirements 202
Ports 203
Security exclusions 203
User role and persona requirements 203
View the Details page 206
View the Configuration page 207
View the Tanium Content page 207
View the Support page 208
View the About page 208
Configure Tanium Security Browser Connector for Microsoft Edge for Business 209
Create a Microsoft Edge for Business configuration policy 209
Enable the Tanium Security Browser Connector for Microsoft Edge for Business integration 211
Configure the Tanium Security Browser Connector for Microsoft Edge for Business 211
Manage the Tanium Security Browser Connector for Microsoft Edge for Business 214
View Tanium Security Browser Connector for Microsoft Edge for Business configuration 214

©2026 Tanium Inc. All Rights Reserved

Rotate the Tanium Security Browser Connector for Microsoft Edge for Business API token .. 214
Revoke the Tanium Security Browser Connector for Microsoft Edge for Business API token 215
Disable the Tanium Security Browser Connector for Microsoft Edge for Business integration 216
Use Tanium Security Browser Connector for Microsoft Edge for Business data 217
View Tanium Security Browser Connector for Microsoft Edge for Business reports and dashboards 217
Include Security Browser Connector data in a report 218
Export Security Browser Connector data using Tanium Connect 219
Troubleshooting 219
Collect logs 219
Cannot retrieve browser use data from Microsoft Edge for Business instances 220
Cannot properly view browser use data from multiple endpoints 220

Troubleshooting 221
Contact Tanium Support 221

©2026 Tanium Inc. All Rights Reserved

Integrations Gallery overview

With Integrations Gallery, you can discover, configure, and manage integrations between third parties and Tanium.

Tanium Integrations Gallery simplifies and accelerates the process of connecting the Tanium platform with key technology partners like Microsoft and ServiceNow. It enables customers to discover integrations effortlessly, providing a clear view of the solutions and integrations that are available.

Benefits of Tanium Integrations Gallery

Discover integrations across tools

Get visibility into integrations with Microsoft, ServiceNow, and more to maximize value across the security and IT operation ecosystem. The streamlined integration process removes friction, making Tanium a seamless extension to ecosystem partner solutions.

Streamlined deployment process

Integrations Gallery replaces the manual setup process with a modern, intuitive, and self-sufficient one. Customers no longer need to rely on teams of experts to deploy and maintain integration solutions.

Reliability and automation for IT, Risk, and SecOps teams

Integrations Gallery eliminates complexity concerns that are a barrier to adoption, reduces the risk of limited or broken integrations, and improves overall stability and ease of use.

Complete visibility into available solutions

The Integrations Gallery workbench includes an **Integrations** section that lists all available integrations, with partners such as Microsoft, ServiceNow, and ScreenMeet.

©2026 Tanium Inc. All Rights Reserved

Interoperability with other Tanium products

Account Management

Integrations Gallery provides access to link your Tanium installation to your Tanium Account. For more information, see .

©2026 Tanium Inc. All Rights Reserved

Getting started with Integrations Gallery

Follow these steps to configure and use Integrations Gallery.

Step 1: Configure Integrations Gallery

For more information, see Configuring Integrations Gallery on page 29.

Step 2: Discover integrations

Access Integrations Gallery

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, filter the list of integrations:
    - Filter by clicking on each category:
        - All
        - AI/ML Platforms
        - IT Asset Management
        - IT Operations Management
        - IT Service Management
        - IT Support
        - Risk Management

©2026 Tanium Inc. All Rights Reserved

        - Security Operations
        - Vulnerability Management
    - Filter by **Enabled**:
        - All
        - Yes
        - No
    - Filter by **Offered By**:
        - All
        - Tanium
        - Partners
    - Filter by selecting a **Solution**
    - Filter by selecting a **Partner**
    - Filter by text searching

View featured integrations

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Featured Integrations** section, read about each integration and click on the video to learn more.
3. Click on the integration name to manage the integration.

Manage integrations

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.

©2026 Tanium Inc. All Rights Reserved

2. In the **Integrations** section, click on each integration tile to view more details and configuration options.

    - **Details**: includes the integration service enablement and configuration status and a link to access the integration
    - **Configuration**: includes configuration options and user roles for the integration
    - **Tanium Content**: includes reports or dashboards specific to the integration usage (not available for all integrations)
    - **About**: includes more information about the integration

©2026 Tanium Inc. All Rights Reserved

Integrations Gallery requirements

Review the requirements before you install and use Integrations Gallery.

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium license that includes Integrations Gallery. For more information about how to get Integrations Gallery, see Tanium Solutions & Bundles.
- Tanium™ Core Platform servers
- Tanium™ Console

Solution dependencies

Other Tanium solutions are required for Integrations Gallery to function (required dependencies) or for specific Integrations Gallery features to work (feature-specific dependencies). The installation method that you select determines if the Tanium Server automatically imports dependencies or if you must manually import them.



Note: Some Integrations Gallery dependencies have their own dependencies, which you can see in the lists of required and feature-specific dependencies below. Where a dependency links to its own user guide, that link opens the guide for the latest version of the solution, not necessarily the minimum version that Integrations Gallery requires.

Tanium recommended installation

If you select **Tanium Recommended Installation** when you import Integrations Gallery, the Tanium Server automatically imports all your licensed solutions at the same time. For more information, see Tanium Console User Guide: Import all modules and services.

©2026 Tanium Inc. All Rights Reserved

Import specific solutions

If you select only Integrations Gallery to import, the Tanium Server automatically imports the latest available versions of any required dependencies that are missing. If some required dependencies are already imported but their versions are earlier than the minimum required for Integrations Gallery, the server automatically updates those dependencies to the latest available versions.

Required dependencies

Integrations Gallery has the following required dependencies:

- Tanium™ Account Management Broker
- Tanium™ Core Content
- Tanium™ Feature Definitions
- Tanium™ Feature Flag
- Tanium™ Interact
- Tanium™ Reporting
- Tanium™ Secrets

Feature-specific dependencies

If you select only Integrations Gallery to import, you must manually import or update its feature-specific dependencies regardless of Tanium Console or Tanium Core Platform versions. Integrations Gallery has the following feature-specific dependencies:

- Tanium™ Asset for using Tanium Connector for Microsoft Intune
- Tanium™ Endpoint Provider Service for using Tanium Connector for Microsoft Intune
- Tanium™ Gateway for Security Copilot integration
- Tanium™ Screen Sharing for ScreenMeet integration

©2026 Tanium Inc. All Rights Reserved

Tanium™ Module Server

Integrations Gallery is installed and runs as a service on the Module Server host computer. The impact on the Module Server is minimal and depends on usage.

For more information about Module Server sizing in a Windows deployment, see Tanium Core Platform User Guide for Windows Deployments: Host system sizing guidelines.

Endpoints

Integrations Gallery does not deploy packages to endpoints. For more information about Tanium Client operating system support, see Tanium Client Management User Guide: Client version and host system requirements.

Host and network security requirements

Specific ports and processes are needed to run Integrations Gallery.

Ports

Integrations Gallery requires no specific open ports to enable communication, but individual integrations might require open ports. For more information, see the page for that integration.

Best Practice: Configure firewall policies to open ports for Tanium traffic with TCP-based rules instead of application identity-based rules. For example, on a Palo Alto Networks firewall, configure the rules with service objects or service groups instead of application objects or application groups.

For more information about Tanium Cloud ports, see Host and network security requirements.

Security exclusions

If antivirus (AV) or other security software is in use in the environment to monitor and block unknown host system processes, Tanium requires that a security administrator create exclusions to allow the Tanium processes to run without interference. This software can include security applications that are included with an endpoint operating system, such as fapolicyd on some Linux distributions, or

©2026 Tanium Inc. All Rights Reserved

Microsoft Defender on Windows. The configuration of these exclusions varies depending on the security software.

For more information about security exclusions to define across Tanium, see Reference: Endpoint security exclusions. For Windows-based Tanium Core Platform deployments, see Tanium Core Platform Server security exclusions.

Note: If the required exclusions are not configured, or if Tanium suspects interference from AV or security software, Tanium might require you to remove or disable the AV or security software temporarily for the purposes of troubleshooting and restore it once troubleshooting is complete.

User role requirements

Predefined roles grant the following permissions, which are required to use Integrations Gallery functionality:

- solution permissions on page 23
- administration and platform content permissions on page 24: The solution permissions automatically provide some of these permissions.

Some Integrations Gallery solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to Integrations Gallery. If you create custom roles for Integrations Gallery users, be sure to assign all the solution permissions and content set permissions that are required for Integrations Gallery functionality. If you are not sure which permissions are required for a custom role, view the permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)
- Provided role permissions
- View effective role permissions
- Configure a custom role

©2026 Tanium Inc. All Rights Reserved

Integrations Gallery solution permissions

Permission	Integrations Gallery Administrator [1]	Integrations Gallery Operator [1]	Integrations Gallery Viewer [1]
Partner Integration View the Integrations Gallery workbench	✓ SHOW	✓ SHOW	✓ SHOW
Partner Integration Api Use the Integrations Gallery API	✓ EXECUTE	✓ EXECUTE	✓ EXECUTE
Partner Integration Credentials View and configure the Integrations Gallery credentials	✓ READ WRITE DELETE	✓ READ WRITE DELETE	✗
Partner Integration Gallery View and configure the Integrations Gallery	✓ READ WRITE	✓ READ	✓ READ
Partner Integration Gallery Account Management View and configure the Account Management settings in Integrations Gallery	✓ READ WRITE	✓ READ	✓ READ
Partner Integration Gallery Azure Vm Extensions View and configure the Azure VM Extensions integration	✓ READ WRITE	✓ READ WRITE	✓ READ
Partner Integration Gallery Copilot View and configure the Microsoft Copilot for Security integration	✓ READ WRITE	✓ READ WRITE	✓ READ
Partner Integration Gallery Screenmeet View and configure the ScreenMeet	✓ ADMIN	✓ ADMIN	✓ VIEWER

©2026 Tanium Inc. All Rights Reserved

Permission	Integrations Gallery Administrator [1]	Integrations Gallery Operator [1]	Integrations Gallery Viewer [1]
integration	READ WRITE	READ WRITE	READ
Partner Integration Reporting Metrics View reporting metrics in Integrations Gallery	✓ READ	✓ READ	✓ READ

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

Integrations Gallery administration and platform content permissions

Permission	Permission Type	Integrations Gallery Administrator	Integrations Gallery Operator	Integrations Gallery Viewer
Action Group	Administration	✓ READ	✓ READ	✓ READ
Public Key	Administration	✓ READ	✓ READ	✗
Action	Platform	✓ READ WRITE	✓ READ WRITE	✓ READ
Filter Group	Platform	✓ READ	✓ READ	✓ READ
Own Action	Platform	✓ READ	✓ READ	✗
Package	Platform	✓	✓	✓

©2026 Tanium Inc. All Rights Reserved

Permission	Permission Type	Integrations Gallery Administrator	Integrations Gallery Operator	Integrations Gallery Viewer
		READ	READ	READ
Plugin	Platform	✓ READ EXECUTE	✓ READ EXECUTE	✓ READ EXECUTE
Sensor	Platform	✓ READ	✓ READ	✓ READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

©2026 Tanium Inc. All Rights Reserved

Installing Integrations Gallery

About this task

Use Tanium Console **Solutions** page to install Integrations Gallery and choose either automatic or manual configuration:

- Automatic configuration with default settings: Integrations Gallery is installed with any required dependencies and other selected products. After installation, the Tanium Server automatically configures the recommended default settings. This option is the best practice for most deployments. For more information about the automatic configuration for Integrations Gallery, see Import Integrations Gallery with default settings on page 26.
- Manual configuration with custom settings: After installing Integrations Gallery, you must manually configure required settings. Select this option only if Integrations Gallery requires settings that differ from the recommended default settings. For more information, see Import Integrations Gallery with custom settings on page 27.

Before you begin

- Read the release notes.
- Review the Integrations Gallery requirements on page 19.
- Assign the correct roles to users for Integrations Gallery. For more information, see User role requirements on page 22.
    - To import the Integrations Gallery solution, you must be assigned the Administrator reserved role.

Import Integrations Gallery with default settings

Use default settings to get started with installing Integrations Gallery without extra configuration steps.

You can set the Integrations Gallery action group to target the **No Computers** filter group by enabling

©2026 Tanium Inc. All Rights Reserved

restricted targeting before importing Integrations Gallery. This option enables you to control tools deployment through scheduled actions that are created during the import and that target the tools action group. For example, you might want to test tools on a subset of endpoints before deploying the tools to all endpoints. In this case, you can manually deploy the tools to an action group that you configured to target only the subset. To configure an action group, see Targeting actions through action groups. To enable or disable restricted targeting, see Tools deployment and restricted targeting.

To import Integrations Gallery and configure default settings, see Tanium Console User Guide: Import all modules and services. To verify that the correct version is installed after the import, see Verify Integrations Gallery version on page 28.

Import Integrations Gallery with custom settings

To import Integrations Gallery without automatically configuring default settings, be sure to clear the **Apply All Tanium recommended configurations** option while performing the steps in Tanium Console User Guide: Import or update specific solutions. When you import with custom settings, default settings are not configured.

Manage solution dependencies

When you start the Integrations Gallery workbench for the first time, the Tanium Server checks whether all the Tanium modules and shared services (solutions) that are required for Integrations Gallery are installed at the required versions. The Integrations Gallery workbench cannot load unless all required dependencies are installed. If you selected **Tanium Recommended Installation** when you imported Integrations Gallery , the Tanium Server automatically imported all your licensed solutions at the same time. Otherwise, if you manually imported Integrations Gallery and did not import all its dependencies, Tanium Console displays a banner that lists the dependencies and the required versions.

1. Install the dependencies as described in Import or update specific solutions.
2. Open the **Integrations Gallery Overview** page. From the Main menu, go to **Shared Services** > **Integrations Gallery**. Verify that the Console no longer displays a banner to list missing dependencies.

Upgrade Integrations Gallery

©2026 Tanium Inc. All Rights Reserved

Verify Integrations Gallery version

After you import or upgrade Integrations Gallery, verify that the correct version is installed.

1. Refresh your browser.
2. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
3. To display version information, click Info .

Troubleshoot issues

About this task

If you experience issues with installing Integrations Gallery, you can troubleshoot issues. For more information, see Troubleshooting Integrations Gallery on page 221.

©2026 Tanium Inc. All Rights Reserved

Configuring Integrations Gallery

Configure Integrations Gallery

Link your Account Portal

Link your Account Portal to view artifacts related to your Tanium instance.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. Click Settings and then click **Link Account Portal**.

   > **Tip:** To link a different Tanium Server instance, click **Move** and then enter information to link the different instance. For more information, see Tanium Account User Guide: Moving a Tanium instance to a different Tanium account.

3. Link a Tanium instance. For more information, see Tanium Account User Guide: Moving a Tanium instance to a different Tanium account.

Move your Tanium Account

About this task

You can link a different Tanium Server instance, but moving the linkage can cause some integrations to stop working or change behavior.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. Click Settings and then click **Move**.
3. Enter the **Username** for the new account to which you want to move the instance and click **Move**.
4. Click the link that appears in the dialog, and sign in to your Tanium Account using the new account. For more information, see .

©2026 Tanium Inc. All Rights Reserved

5. When prompted, click **Yes** to grant your Tanium instance the necessary access privileges to communicate with the new account in your Tanium Account.

Set up Integrations Gallery users

You can use the following set of predefined user roles to set up Integrations Gallery users.

For more information about specific permissions for each role, see User role requirements on page 22.

For more information about assigning user roles, see Tanium Core Platform User Guide: Manage role assignments for a user.

Tip: To provide just-in-time access or scalable standing access to Integrations Gallery functionality, you can use SCIM provisioning combined with Tanium user groups. This approach lets you manage user access at scale or ad hoc through your identity provider, without creating users individually in Tanium. For more information, see Provision users into Tanium user groups with SCIM.

Integrations Gallery Administrator

Assign the **Integrations Gallery Administrator** role to users who manage the configuration of Integrations Gallery. This role can perform the following tasks:

- Configure Integrations Gallery service settings.
- View and modify the configuration of all integrations in Integrations Gallery.

Integrations Gallery Operator

Assign the **Integrations Gallery Operator** role to users who manage the configuration of all integrations in Integrations Gallery.

Integrations Gallery Viewer

Assign the **Integrations Gallery Viewer** role to users who need visibility into Integrations Gallery data. This role can perform the following tasks:

- View Integrations Gallery service settings.

©2026 Tanium Inc. All Rights Reserved

- View configurations of all integrations.

©2026 Tanium Inc. All Rights Reserved

Managing the Microsoft Azure VM Extensions integration

Tanium provides Azure virtual machine (VM) extensions that can be installed to automatically deploy the Tanium Client on Microsoft Azure VMs and VM Scale Sets. After deploying Tanium Client to the Microsoft Azure VMs, you can manage the VMs from Tanium Console.

For more information about deploying the Tanium Client in Microsoft Azure environments, see Tanium Client Management User Guide: Deploy the Tanium Client in Microsoft Azure environments using the Tanium Client VM extension.

Requirements

Operating system support in Microsoft Azure

The Tanium Client supports both Windows and Linux VMs in Azure. Supported versions and Linux distributions are the same as for any endpoint; for more information, see Tanium Client Management User Guide: Client version and operating system requirements. However, for Linux VMs in Azure, the Tanium Client VM extension is supported only on Linux distributions that are both endorsed by Microsoft and supported by the Tanium Client. For more information about a list of Linux distributions that are endorsed by Microsoft, see Microsoft Azure Documentation: Endorsed Linux distributions on Azure.

Tanium provides separate Azure VM extensions for Windows and Linux VMs.

Network connectivity

Each VM must be able to connect to https://content.tanium.com for the VM extension to import the files needed to deploy the Tanium Client.

Computer group dependencies

When you first Sign in to Tanium Console after a fresh installation of Tanium Server, the server automatically imports the computer groups that Integrations Gallery requires:

©2026 Tanium Inc. All Rights Reserved

- Integration - All Installed by Azure
- Integration - All Linux Installed by Azure
- Integration - All Windows Installed by Azure

For earlier versions of the Tanium Server, or after upgrading from an earlier version, you must manually create the computer groups. For more information, see Tanium Console User Guide: Create a computer group.

User role requirements

Predefined roles grant the following permissions, which are required to use Microsoft Azure VM Extensions functionality:

- Microsoft Azure VM Extensions solution permissions on page 34
- Microsoft Azure VM Extensions administration, platform content, and global permissions on page 34: The solution permissions automatically provide some of these permissions.

Some Microsoft Azure VM Extensions solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to Microsoft Azure VM Extensions. If you create custom roles for Microsoft Azure VM Extensions users, be sure to assign all the solution permissions and content set permissions that are required for Microsoft Azure VM Extensions functionality. If you are not sure which permissions are required for a custom role, view the permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)
- Provided role permissions
- View effective role permissions
- Configure a custom role

©2026 Tanium Inc. All Rights Reserved

Microsoft Azure VM Extensions solution permissions

Permission	Integration Operator - Azure VM Extensions [1]	Integration Viewer - Azure VM Extensions [1]
Partner Integration View the Integrations Gallery workbench	✓ SHOW	✓ SHOW
Partner Integration Api Use the Integrations Gallery API	✓ EXECUTE	✓ EXECUTE
Partner Integration Gallery View and configure the Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Account Management View the Account Management settings in Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Azure Vm Extensions View and configure the Azure VM Extensions integration	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View reporting metrics in Integrations Gallery	✓ READ	✓ READ

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

Microsoft Azure VM Extensions administration and platform content permissions

Permission	Permission Type	Integration Operator - Azure VM Extensions	Integration Viewer - Azure VM Extensions
Action Group	Administration	✓ READ	✓ READ

©2026 Tanium Inc. All Rights Reserved

Permission	Permission Type	Integration Operator - Azure VM Extensions	Integration Viewer - Azure VM Extensions
Public Key	Administration	✓ READ	✗
Filter Group	Platform	✓ READ	✓ READ
Package	Platform	✓ READ	✓ READ
Plugin	Platform	✓ READ EXECUTE	✓ READ EXECUTE
Sensor	Platform	✓ READ	✓ READ
To view the content sets to which the platform content permissions apply, see View effective role permissions .			

View the Details page

About this task

The **Details** page for the Microsoft Azure VM Extensions integration shows the following information:

- **Service Enablement** toggle
- **Configuration** status
- **Installations** count
- **Initialization Profile File Downloads** count
- **Access** link
- **Usage** reports

©2026 Tanium Inc. All Rights Reserved

- **Client Installations by Azure VM Extensions**
- **Client Installations by All Methods**

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.

View the Configuration page

About this task

The **Configuration** page for the Microsoft Azure VM Extensions integration shows the following information:

- **Tanium Client Initialization Profiles**: For more information, see Create a Tanium Client initialization profile on page 38.
- **Role Assignment**: For more information, see User role requirements on page 33.
- **Computer Groups**: For more information, see Computer group dependencies on page 32.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **Configuration**.

View the Tanium Content page

About this task

The **Tanium Content** page for the Microsoft Azure VM Extensions integration shows the following information:

- **Dashboards**
  - **Deployments using Azure VM Extensions**

©2026 Tanium Inc. All Rights Reserved

        - **Deployments using Azure VM Extensions - Over Time**

- **Reports**

        - **Azure VM Extension Usage**

        - **Deployments using Azure VM Extensions - Over Time**

To view the **Tanium Content** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **Tanium Content**.

View the Support page

About this task

The **Support** page for the Microsoft Azure VM Extensions integration shows the following information:

- **Create Package** button to create a troubleshooting package for support requests

To view the **Support** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **Support**.

View the About page

About this task

The **About** page for the Microsoft Azure VM Extensions integration shows the following information:

- **Tanium Client Deployment Automation** video

- **VM Extension for Linux**

©2026 Tanium Inc. All Rights Reserved

- **VM Extension for Windows**
- **Tanium Initialization Files**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **About**.

Enable the integration

About this task

To get started, you must enable the Microsoft Azure VM Extensions integration.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **Enable** and then confirm your selection.

Result

You can also click **Open Azure Portal** to access the Microsoft Azure portal.

Create a Tanium Client initialization profile

About this task

You can create a Client initialization profile in Integrations Gallery to create the tanium-init.dat file that can be used to deploy the Tanium Client to Microsoft Azure VMs and VM Scale Sets.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **Configuration** and then click **Create Profile**.
    a. In the **Details** section, enter a **Name** and optionally a **Description**, and select a content set.

©2026 Tanium Inc. All Rights Reserved

b. In the **Configuration** section, configure any Tanium Server and Client options.

- Enter a comma-separated list of Tanium **Server Names**, used to manage the Clients. Entering a server name automatically adds the **server_name_list** Client setting. Include host names in any of the following formats:

Tanium Server name format	Format example
host name without port number	`host.example.com`
host name with port number	`host.example.com:8080`
IP address without port number	`192.0.2.10`
IP address with port number	`192.0.2.10:8080`

- Enter a Tanium **Server Port**, used for establishing a connection with each Tanium Server. Entering a server port automatically adds the **server_port** Client setting. If you specify a host name with port number or IP address with port number in the **Server Names** list, that port number takes priority over this **Server Port** value.

- If deployed Clients must connect through a proxy server, select one of the following **Proxy** options:

    - **PAC file** (Windows endpoints only): Use a proxy auto-config (PAC) file to configure the proxy on endpoints. Selecting this option automatically adds the **proxy_auto_config_address** Client setting. Configure the URL of the PAC file for the value.

    - **Proxy Server**: Use specific addresses to connect endpoints through a proxy server. Selecting this option automatically adds the **proxy_servers** Client setting. Configure the addresses of proxy servers for the value.

      For more information about using a proxy server, see Tanium Client Management User Guide: Connect through an HTTPS forward proxy server.

- Enter a **Log Level** for the Tanium Client on targeted endpoints, associated with the **log_verbosity_level** Client setting. The following values are best practices for specific scenarios:

©2026 Tanium Inc. All Rights Reserved

- `1` (default): Use this value during normal operation.
- `41`: Use this value during troubleshooting.
- `91` or higher: Use this value for full logging, for short periods of time only.

> **Note:** A value of `0` disables logging. As a best practice, do not disable logging.

- To add a custom tag to the Client during deployment, click **Add Custom Tag** and enter a tag name. The `InstalledByAzure` tag is included by default so that you can later easily target Clients that were installed using the Tanium Client VM extension in Integrations Gallery.

4. Click **Create**.

Obtain the tanium-init.dat file for deployment

About this task

You can copy the base64-encoded version of the tanium-init.dat file, or optionally download the file to use when installing the Tanium Client VM extension.

> **Tip:** You use the base64-encoded contents during installation of the extension. However, you can download the tanium-init.dat file if you use a parameter in template or policy JSON to import the file directly or if you need the file for other deployment purposes.

©2026 Tanium Inc. All Rights Reserved

Important:

Be careful not to allow the tanium-init.dat file to be distributed or stored outside of your organization, such as in a publicly accessible source code repository or any other location accessible from the public internet. Limit the distribution to specific use in the deployment of Tanium Clients.

Though this file does not contain private keys and cannot be used to provide control over a Tanium environment, a user with malicious intent could use it to connect an unapproved Client and use this unauthorized access to learn how your organization is using Tanium.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **Configuration**.
4. Copy the base64-encoded contents of a file for a profile, or download the file for one or more profiles:
   - To copy the base64-encoded contents of a tanium-init.dat file for a profile, click Copy base64-encoded profile to clipboard in the row for the profile.
   - To download the tanium-init.dat files for one or more profiles, click **Configuration**, select one or more profiles, and then click Download.

     Tip: If you select multiple profiles, you download a ZIP file that contains the tanium-init.dat file for each selected profile.
5. Follow the steps in Tanium Client Management User Guide: Installation methods for the Tanium Client VM extension.

Result

Tip: You can click **Download All** to download a ZIP file of all profiles.

Disable the integration

©2026 Tanium Inc. All Rights Reserved

About this task

Disable the Microsoft Azure VM Extensions integration to stop deploying Tanium Client on Microsoft Azure VMs and VM Scale Sets.

Important: If you disable the Microsoft Azure VM Extensions integration, the VM extension is still installed in Azure. Remove the extension if you want to fully remove the integration. For more information, see Microsoft Azure documentation: Rerun a VM extension.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. On the **Details** page, click the **Service Enablement** toggle.

Troubleshoot the Azure VM Extensions integration

If the Microsoft Azure VM Extensions integration is not performing as expected, you might need to troubleshoot issues or change settings.

Collect logs

About this task

The information is saved as a ZIP file that you can download with your browser. The ZIP file is also known as a support bundle.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure VM Extensions**.
3. Click **Support**.
4. Click **Create Package**. An integrations-gallery-support-bundle-[timestamp].zip file downloads to the local download directory.
5. Contact Tanium Support to determine the best option to send the ZIP file. For more information, see View the Support page on page 37.

Cannot install the Tanium Client VM extension on Microsoft Azure VMs

©2026 Tanium Inc. All Rights Reserved

About this task

If you encounter an issue with the installation of the Tanium Client VM extension, check the following items:

1. Make sure the OS on the VM is both supported by the Tanium Client and endorsed by Microsoft. For more information, see Operating system support in Microsoft Azure on page 32.
2. If an ARM template or an Azure Policy fails to evaluate, review the template or policy for errors. For more information, see Microsoft Azure Documentation: Azure virtual machine extensions and features and contact Microsoft Support if necessary. You can try installing the extension on an endpoint manually to make sure the extension itself is working with the VM. For more information, see Tanium Client Management User Guide: Manually install the extension using the Azure Portal, Azure CLO, or Azure PowerShell.
3. If you corrected all issues in a template or policy and continue to experience installation issues, or if you cannot manually install the extension, Contact Tanium Support on page 221 for assistance.

©2026 Tanium Inc. All Rights Reserved

Managing the Microsoft Azure Arc integration

Tanium provides a native extension for Microsoft Azure Arc that can be installed to automatically deploy the Tanium Client on Azure Arc-connected machines. After you enable the Azure Arc integration, you can deploy Tanium Client to Azure Arc-connected machines and manage the machines from Tanium Console.

Requirements

Operating system support on Microsoft Azure Arc

The Tanium Client supports both Windows and Linux Arc-connected machines. Supported versions and Linux distributions are the same as for any endpoint; for more information, see Tanium Client Management User Guide: Client version and operating system requirements.

Tanium provides separate Azure Arc extensions for Windows and Linux.

Azure Arc prerequisites

Before you deploy the Tanium Client Azure Arc extension, confirm the following requirements are met:

- Each target machine must already be connected to Azure Arc as an Arc-enabled machine, with the Azure Connected Machine agent installed. The Tanium Azure Arc extension does not connect machines to Azure Arc or install the Connected Machine agent. For more information, see Microsoft Azure Documentation: Azure Arc-enabled servers overview and Microsoft Azure Documentation: Azure Connected Machine agent overview.
- If your subscription uses Azure Arc extension allow lists, add the `Tanium.Client` publisher to the allow list before you deploy the extension. Otherwise, the installation is blocked without a visible error. For more information, see Microsoft Azure Documentation: Manage extension allow and block lists.

©2026 Tanium Inc. All Rights Reserved

Network connectivity

Each Arc-connected machine must be able to connect to https://content.tanium.com for the extension to import the files needed to deploy the Tanium Client.

Computer group dependencies

When you first Sign in to Tanium Console after a fresh installation of Tanium Server, the server automatically imports the computer groups that Integrations Gallery requires:

- Integration - All Installed by Azure Arc
- Integration - All Linux Installed by Azure Arc
- Integration - All Windows Installed by Azure Arc

For earlier versions of the Tanium Server, or after upgrading from an earlier version, you must manually create the computer groups. For more information, see Tanium Console User Guide: Create a computer group.

User role requirements

Predefined roles grant the following permissions, which are required to use Microsoft Azure Arc functionality:

- Microsoft Azure Arc solution permissions on page 46
- Microsoft Azure Arc administration, platform content, and global permissions on page 47: The solution permissions automatically provide some of these permissions.

Some Microsoft Azure Arc solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to Microsoft Azure Arc. If you create custom roles for Microsoft Azure Arc users, be sure to assign all the solution permissions and content set permissions that are required for Microsoft Azure Arc functionality. If you are not sure which permissions are required for a custom role, view the permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)

©2026 Tanium Inc. All Rights Reserved

- Provided role permissions
- View effective role permissions
- Configure a custom role

Microsoft Azure Arc solution permissions

Permission	Integration Operator - Azure Arc [1]	Integration Viewer - Azure Arc [1]
Partner Integration View the Integrations Gallery workbench	✓ SHOW	✓ SHOW
Partner Integration Api Use the Integrations Gallery API	✓ EXECUTE	✓ EXECUTE
Partner Integration Gallery View and configure the Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Account Management View the Account Management settings in Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Azure Arc View and configure the Azure Arc integration	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View reporting metrics in Integrations Gallery	✓ READ	✓ READ

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

©2026 Tanium Inc. All Rights Reserved

Microsoft Azure Arc administration and platform content permissions

Permission	Permission Type	Integration Operator - Azure Arc	Integration Viewer - Azure Arc
Action Group	Administration	READ	READ
Public Key	Administration	READ	
Filter Group	Platform	READ	READ
Package	Platform	READ	READ
Plugin	Platform	READ EXECUTE	READ EXECUTE
Sensor	Platform	READ	READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

Enable the integration

About this task

To get started, you must enable the Microsoft Azure Arc integration.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.
3. Click **Enable** and then confirm your selection.

Result

©2026 Tanium Inc. All Rights Reserved

You can also access the Microsoft Azure portal by clicking **Open Azure Portal**.

Create a Tanium Client initialization profile

About this task

You can create a Client initialization profile in Integrations Gallery to create the tanium-init.dat file that can be used to deploy the Tanium Client to Azure Arc-connected machines.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.
3. Click **Configuration** and then click **Create Profile**.
    a. In the **Details** section, enter a **Name** and optionally a **Description**, and select a content set.
    b. In the **Configuration** section, configure any Tanium Server and Client options.
        - Enter a comma-separated list of Tanium **Server Names**, used to manage the Clients. Entering a server name automatically adds the **server_name_list** Client setting. Include host names in any of the following formats:

Tanium Server name format	Format example
host name without port number	`host.example.com`
host name with port number	`host.example.com:8080`
IP address without port number	`192.0.2.10`
IP address with port number	`192.0.2.10:8080`

        - Enter a Tanium **Server Port**, used for establishing a connection with each Tanium Server. Entering a server port automatically adds the **server_port** Client setting. If you specify a host name with port number or IP address with port number in the **Server Names** list, that port number takes priority over this **Server Port** value.
        - If deployed Clients must connect through a proxy server, select one of the following **Proxy** options:
            - **PAC file** (Windows endpoints only): Use a proxy auto-config (PAC) file

©2026 Tanium Inc. All Rights Reserved

to configure the proxy on endpoints. Selecting this option automatically adds the **proxy_auto_config_address** Client setting. Configure the URL of the PAC file for the value.

- **Proxy Server**: Use specific addresses to connect endpoints through a proxy server. Selecting this option automatically adds the **proxy_servers** Client setting. Configure the addresses of proxy servers for the value.

  For more information about using a proxy server, see Tanium Client Management User Guide: Connect through an HTTPS forward proxy server.

- Enter a **Log Level** for the Tanium Client on targeted endpoints, associated with the **log_verbosity_level** Client setting. The following values are best practices for specific scenarios:

  - `1` (default): Use this value during normal operation.
  - `41`: Use this value during troubleshooting.
  - `91` or higher: Use this value for full logging, for short periods of time only.

  Note: A value of `0` disables logging. As a best practice, do not disable logging.

- To add a custom tag to the Client during deployment, click **Add Custom Tag** and enter a tag name. The `InstalledByAzureArc` tag is included by default so that you can later easily target Clients that were installed using the Tanium Client Azure Arc extension in Integrations Gallery.

4. Click **Create**.

Obtain the tanium-init.dat file for deployment

About this task

You can copy the base64-encoded version of the tanium-init.dat file, or optionally download the file

©2026 Tanium Inc. All Rights Reserved

to use when installing the Tanium Client Azure Arc extension.

Tip: You use the base64-encoded contents during installation of the extension. However, you can download the tanium-init.dat file if you use a parameter in template or policy JSON to import the file directly or if you need the file for other deployment purposes.

Important:

Be careful not to allow the tanium-init.dat file to be distributed or stored outside of your organization, such as in a publicly accessible source code repository or any other location accessible from the public internet. Limit the distribution to specific use in the deployment of Tanium Clients.

Though this file does not contain private keys and cannot be used to provide control over a Tanium environment, a user with malicious intent could use it to connect an unapproved Client and use this unauthorized access to learn how your organization is using Tanium.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.
3. Click **Configuration**.
4. Copy the base64-encoded contents of a file for a profile, or download the file for one or more profiles:
   - To copy the base64-encoded contents of a tanium-init.dat file for a profile, click Copy base64-encoded profile to clipboard in the row for the profile.
   - To download the tanium-init.dat files for one or more profiles, click **Configuration**, select one or more profiles, and then click Download.

     Tip: If you select multiple profiles, you download a ZIP file that contains the tanium-init.dat file for each selected profile.
5. Follow the steps in Tanium Client Management User Guide: Deploy the Tanium Client to

©2026 Tanium Inc. All Rights Reserved

Azure Arc-connected endpoints.

Result

Tip: You can click **Download All** to download a ZIP file of all profiles.

View the Details page

About this task

The **Details** page for the Microsoft Azure Arc integration shows the following information:

- **Service Enablement** toggle
- **Configuration** status
- **Installations** count
- **Initialization Profile File Downloads** count
- **Access** link to Azure portal
- **Usage** reports
    - **Client Installations by Azure Arc**
    - **Client Installations by All Methods**

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.

View the Configuration page

About this task

The **Configuration** page for the Microsoft Azure Arc integration shows the following information:

©2026 Tanium Inc. All Rights Reserved

- **Tanium Client Initialization Profiles**: For more information, see Create a Tanium Client initialization profile on page 48.
- **Role Assignment**: For more information, see User role requirements on page 45.
- **Computer Groups**: For more information, see Computer group dependencies on page 45.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.
3. Click **Configuration**.

View the Tanium Content page

About this task

The **Tanium Content** page for the Microsoft Azure Arc integration shows the following information:

- **Dashboards**
    - **Deployments using the Azure Arc Extension**
    - **Deployments using the Azure Arc Extension - Over Time**
- **Reports**
    - **Azure Arc Extension Usage**
    - **Deployments using the Azure Arc Extension - Over Time**

To view the **Tanium Content** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.
3. Click **Tanium Content**.

View the About page

©2026 Tanium Inc. All Rights Reserved

About this task

The **About** page for the Microsoft Azure Arc integration shows the following information:

- **Tanium Client Deployment Automation** video
- **Arc Extension for Windows**
- **Arc Extension for Linux**
- **Tanium Initialization Files**
- **Real-Time Visibility Across the Hybrid Estate**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.
3. Click **About**.

Disable the integration

About this task

Disable the Microsoft Azure Arc integration to stop deploying Tanium Client on Azure Arc-connected machines.

Important: If you disable the Microsoft Azure Arc integration, the extension is still installed through Azure Arc. Remove the extension if you want to fully remove the integration. For more information, see Microsoft Azure documentation: Manage VM extensions on Azure Arc-enabled servers.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Azure Arc**.
3. On the **Details** page, click the **Service Enablement** toggle.

©2026 Tanium Inc. All Rights Reserved

Managing the Microsoft Security Copilot integration

Important:

To use the Tanium integration with Microsoft Security Copilot, you must be a:

- Microsoft Security Copilot subscriber
- Tanium customer

For more information on Microsoft Security Copilot, see Microsoft Security documentation: What is Microsoft Security Copilot?.

The Tanium API Plugin for Microsoft Security Copilot enables responses to natural language prompts using Tanium-gathered information and insight. The Security Copilot large language model (LLM) can use Tanium Skills provided by the Tanium API Plugin to query your network, and to respond with the collected information and additional context as needed.

An AI agent (agent) processes and evaluates data from multiple sources to accomplish a task. Agents provide the following benefits:

- Agents are more adaptable than a predefined algorithm.
- Agents adjust to a variety of input data.
- Agents synthesize an aggregated response that considers the available input.

In response to a prompt, a Tanium agent in Microsoft Security Copilot calls other Tanium skills or sub-agents, aggregates the results from each skill, and then generates a summary of the analysis and possible next steps, based on Tanium intelligence and security best practices.

Getting started with the Microsoft Security Copilot integration

©2026 Tanium Inc. All Rights Reserved

About this task

To configure the integration between Tanium and Microsoft Security Copilot:

1. Ensure that you can establish bidirectional network communication between the Tanium Server and Microsoft Security Copilot. For more information, Allow secure network connections between Tanium and Microsoft Security Copilot on page 64.
2. Configure a persona with the required roles to use the Microsoft Security Copilot integration. For more information, Set up Tanium integration with Microsoft Security Copilot users on page 64.
3. Configure the Tanium API Plugin for Microsoft Security Copilot, and generate an API token to authenticate incoming requests from Microsoft Security Copilot to Tanium. For more information, see Configure Tanium API Plugin for Microsoft Security Copilot on page 66 and Using the Tanium API plugin for Microsoft Security Copilot on page 71.
4. (Optional) Configure Tanium agents to integrate with Microsoft Security Copilot. For more information, see Configure Tanium agents for Microsoft Security Copilot on page 68.
5. Submit prompts in Microsoft Security Copilot to gather information about your Tanium environment.

Tanium functionality available for Microsoft Security Copilot integration

Tanium functionality	Description
Tanium API Plugin	Use the Tanium API Plugin to query endpoints for real-time Tanium data. This plugin enables responses to natural language prompts using Tanium-gathered information and insight. For more information, see Using the Tanium API plugin for Microsoft Security Copilot on page 71 .
Tanium Security Health Analyzer Agent	Use the Tanium Security Health Analyzer Agent to quickly evaluate Microsoft Defender status and identify potentially vulnerable endpoints that do not have the latest Microsoft Defender updates. This agent analyzes an endpoint based on host name, returning Microsoft defender installation status and general endpoint health. For more information, see Using the Tanium Security Health Analyzer Agent on page 87 . **Note:** The Tanium Security Health Analyzer Agent requires a license for Microsoft Defender as part of a Microsoft 365 subscription.

©2026 Tanium Inc. All Rights Reserved

Tanium functionality	Description
Tanium Security Triage Agent	Use the Tanium Security Triage Agent to quickly triage and assess Threat Response alerts. This agent analyzes a Tanium Threat Response alert, calls additional subagents and skills to return information, and returns a summary. For more information, see Using the Tanium Security Triage Agent on page 89 .
Tanium Security Triage Agent with Identity Insights	Use the Tanium Security Triage Agent with Identity Insights to combine Threat Response alert triage with identity information from Microsoft Entra. This agent analyzes a Tanium Threat Response alert, calls additional subagents and skills to return information, associates an Entra ID job title with the assessment, and returns a summary. For more information, see Using the Tanium Security Triage Agent with Identity Insights on page 92 . **Note:** The Tanium Security Triage Agent with Identity Insights requires a subscription to Microsoft Security Copilot, a hybrid Microsoft Entra ID environment, and a Microsoft Sentinel data lake tier subscription.

Requirements for the Microsoft Security Copilot integration

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium™ Core Platform servers
- Tanium™ Client: No client requirements.

> **Note:** For the best results, deploy Tanium Client 7.6 or later to endpoints in your environment. Endpoints running Tanium Client 7.5 and earlier might provide slower responses to questions.

Solution dependencies

Other Tanium solutions are required for Integrations Gallery to function (required dependencies) or for specific Integrations Gallery features to work (feature-specific dependencies). The installation

©2026 Tanium Inc. All Rights Reserved

method that you select determines if the Tanium Server automatically imports dependencies or if you must manually import them.

> **Note:** Some Integrations Gallery dependencies have their own dependencies, which you can see by clicking the links in the lists of Required dependencies on page 57 and Feature-specific dependencies on page 58. Note that the links open the user guides for the latest version of each solution.

TANIUM RECOMMENDED INSTALLATION

If you select **Tanium Recommended Installation** when you import Integrations Gallery, the Tanium Server automatically imports all your licensed solutions at the same time. For more information, see Tanium Console User Guide: Import all modules and services.

IMPORT A SPECIFIC SOLUTION

If you select only Integrations Gallery to import, the Tanium Server automatically imports the latest available versions of any required dependencies that are missing. If some required dependencies are already imported but their versions are not the latest, the Server automatically updates those dependencies to the latest available versions.

REQUIRED DEPENDENCIES

The Microsoft Security Copilot integration has the following required dependencies:

- Tanium Interact to view Tanium Console Question Results pages
- Tanium Gateway for Microsoft Security Copilot integration with Tanium

Third-party software requirements for Microsoft Security Copilot integration

Tanium agent	Required dependencies
Tanium Security Triage Agent, Tanium Security Triage Agent with Identity Insights	• Tanium Direct Connect to establish a direct connection with endpoints and retrieve process artifact information • Tanium Threat Response to retrieve alert information and related process details

©2026 Tanium Inc. All Rights Reserved

Tanium agent	Required dependencies
	• Tanium™ Partner Integration for Microsoft Security Copilot integration with Tanium, and to automatically create the **Microsoft Security Copilot Operator** persona
Tanium Security Health Analyzer Agent	No additional dependencies

FEATURE-SPECIFIC DEPENDENCIES

The Tanium API Plugin for Microsoft Security Copilot has the following feature-specific dependencies:

- Tanium Asset to prompt Microsoft Security Copilot for information related to Software Bill of Materials (SBOM)
- Tanium Certificate Manager to prompt Microsoft Security Copilot for information related to encryption certificates
- Tanium Comply to prompt Microsoft Security Copilot for vulnerability information
- Tanium Direct Connect to view the Threat Response Live Connections page after prompting Microsoft Security Copilot for a list of running endpoint processes
- Tanium Discover to prompt Microsoft Security Copilot for information related to Discover content
- Tanium Enforce to prompt Microsoft Security Copilot for information related to Enforce content
- Tanium Impact to prompt Microsoft Security Copilot for information related to Impact content
- Tanium Incident Response to prompt Microsoft Security Copilot for information related to service module, service process, and related information
- Tanium Index to prompt Microsoft Security Copilot for information related to file metadata
- Tanium SBOM to prompt Microsoft Security Copilot for information related to SBOM
- Tanium Threat Response to prompt Microsoft Security Copilot for information related to

©2026 Tanium Inc. All Rights Reserved

processes and process details

Third-party software

The Tanium integration for Microsoft Security Copilot requires a Microsoft Security Copilot subscription. Certain plugins and agents have additional third-party software requirements.

Third-party software requirements for Microsoft Security Copilot integration

Tanium functionality	Third-party software requirements
Tanium Security Triage Agent with Identity Insights	• Hybrid Microsoft Entra ID environment • Microsoft Sentinel data lake tier subscription
Tanium Security Health Analyzer Agent	Microsoft Defender license as part of a Microsoft 365 subscription

User role and persona requirements

The following table lists the roles to associate with the **Microsoft Security Copilot Operator** persona, required to configure the Microsoft Security Copilot integration. For more information on personas, see Tanium Console User Guide: Managing personas.

Roles associated with **Microsoft Security Copilot Operator** persona

Role	Description
Gateway User	System role to generate an API token that has permission to submit Gateway queries
Integration Operator - Security Copilot	System role to use the Microsoft Security Copilot integration
Interact Power User	System role to view Tanium Console question results
Threat Response User	System role to use skills related to Threat Response, and to use the Tanium Security Triage Agent and Tanium Security Triage Agent with Identity Insights

Predefined roles grant the following permissions, which are required to use Microsoft Security Copilot integration functionality:

- Table 11. Microsoft Security Copilot integration solution permissions on page 60

©2026 Tanium Inc. All Rights Reserved

- Table 12. Microsoft Security Copilot integration administration, platform content, and global permissions on page 61: The solution permissions automatically provide some of these permissions.

Some Microsoft Security Copilot integration solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to the Microsoft Security Copilot integration. If you create custom roles for Microsoft Security Copilot integration users, be sure to assign all the solution permissions and content set permissions that are required for Microsoft Security Copilot integration functionality. If you are not sure which permissions are required for a custom role, view the permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)
- Provided role permissions
- View effective role permissions
- Configure a custom role

Microsoft Security Copilot integration solution permissions

Permission	Integration Operator - Security Copilot [1]	Integration Viewer - Security Copilot [1]
Partner Integration View the Integrations Gallery workbench	✓ SHOW	✓ SHOW
Partner Integration Api Use the Integrations Gallery API	✓ EXECUTE	✓ EXECUTE
Partner Integration Credentials View and configure the Integrations Gallery credentials	✓ READ	✗
Partner Integration Gallery View and configure the Integrations Gallery	✓ READ	✓ READ

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Operator - Security Copilot [1]	Integration Viewer - Security Copilot [1]
Partner Integration Gallery Account Management View the Account Management settings in Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Copilot View and configure the Security Copilot integration	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View reporting metrics in Integrations Gallery	✓ READ	✓ READ
Security Copilot Operate the Security Copilot integration	✓ OPERATOR	✗

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

Microsoft Security Copilot integration administration, platform content, and global permissions

Permission	Permission Type	Integration Operator - Security Copilot	Integration Viewer - Security Copilot
Action Group	Administration	✓ READ	✓ READ
Filter Group	Platform	✓ READ	✓ READ
Package	Platform	✓ READ	✓ READ
Plugin	Platform	✓	✓

©2026 Tanium Inc. All Rights Reserved

Permission	Permission Type	Integration Operator - Security Copilot	Integration Viewer - Security Copilot
		READ EXECUTE	READ EXECUTE
Sensor	Platform	✓ READ	✓ READ
To view the content sets to which the platform content permissions apply, see View effective role permissions .			

View the Details page

About this task

The **Details** page for the Microsoft Security Copilot integration shows the following information:

- **Service Enablement** toggle
- **Configuration** status
- **Access** link
- **Usage** reports
    - **Unique Users for Copilot**
    - **Tanium Requests by Copilot**
    - **Most Used Sensors**

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Security Copilot**.

View the Configuration page

About this task

©2026 Tanium Inc. All Rights Reserved

The **Configuration** page for the Microsoft Security Copilot integration shows the following information:

- **Register Tanium with Microsoft Security Copilot** configuration
- **Role Assignment**: For more information, see User role and persona requirements on page 59.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Security Copilot**.
3. Click **Configuration**.

View the About page

About this task

The **About** page for the Microsoft Security Copilot integration shows the following information:

- **AI Powered Real-Time Insights** video
- **Enhanced Security**
- **Vulnerability Management**
- **Data-Driven Decision Making**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Security Copilot**.
3. Click **About**.

Configuring the Microsoft Security Copilot integration

To configure the integration between Tanium and Microsoft Security Copilot, configure a persona with the roles required to use the Microsoft Security Copilot integration, configure the Tanium

©2026 Tanium Inc. All Rights Reserved

API Plugin for Microsoft Security Copilot, generate an API token to authenticate incoming requests from Microsoft Security Copilot to Tanium, and configure Tanium agents to integrate with Microsoft Security Copilot.

Allow secure network connections between Tanium and Microsoft Security Copilot

Best Practice: For the best results, migrate your deployment to Tanium™ Cloud. Tanium Cloud infrastructure establishes secure network connections between Tanium and Microsoft Security Copilot. For more information, contact Support.

The Microsoft Security Copilot integration requires bidirectional network communication between the Tanium Server and Security Copilot. Ensure that the Microsoft Security Copilot egress IP address for your Azure region can establish bidirectional communication with the Tanium Server over port 443/TCP (HTTPS), and decrypt incoming traffic to the Tanium Server to verify that the traffic originates from a trusted source. For more information, see .

Show Microsoft Security Copilot integration configuration

By default, the Microsoft Security Copilot integration settings are hidden. To contact Tanium Support for help, sign in to the Tanium Customer Community.

Set up Tanium integration with Microsoft Security Copilot users

About this task

Important:

By default, the predefined **Microsoft Security Copilot Operator** persona does not have any roles assigned. You must assign roles to this persona before using the Security Copilot integration. Configure the integration using your default persona. For more information about how to assign roles, see Tanium Console User Guide: Configure role assignments for a user. For more information about how to assign personas, see Tanium Console User Guide: Manage user assignments for a persona.

©2026 Tanium Inc. All Rights Reserved


Assign the following system roles to the predefined **Microsoft Security Copilot Operator** persona to provide the permissions needed to use the Microsoft Security Copilot integration.

- **Gateway User** system role to generate an API token that has permission to submit Gateway queries
- **Integration Operator - Security Copilot** system role to configure the Microsoft Security Copilot integration
- **Interact Power User** system role to view Tanium Console question results
- **Threat Response User** system role if you want to allow Security Copilot to access Threat Response alerts and related information, or use the Security Triage Agent or Security Triage Agent with Identity Insights

  This role also has the **Threat Response Live Connection write** permission, used to allow Microsoft Security Copilot to establish a direct connection with an endpoint and get process information.

Assign users to the **Microsoft Security Copilot Operator** persona to allow these users access to the Microsoft Security Copilot integration.

1. From the Main menu, go to **Administration** > **Permissions** > **Personas**.
2. Enter `Microsoft Security Copilot Operator` in the **Filter items** field, and then click **Microsoft Security Copilot Operator**.
3. Click **Edit Mode**.
4. In the **Roles** section, click **Manage Roles**. The Assign Roles to Persona modal appears.
5. Enter each of the following roles in the **Filter by Name** field, and then select the role: **Gateway User**, **Interact Power User**, **Integration Operator - Security Copilot**, and **Threat Response User**.



6. Click **Apply**.
7. If you want to assign the **Microsoft Security Copilot Operator** persona to a user group, click

©2026 Tanium Inc. All Rights Reserved

Expand ▸ next to the **User Groups** section and click **Manage User Groups**. Select a user group and click **Select**.

8. If you want to assign the **Microsoft Security Copilot Operator** persona to individual users, click Expand ▸ next to the **Users** section and click **Manage Users**. Select users and click **Select**.

9. Click **Save**.

Configure Tanium API Plugin for Microsoft Security Copilot

About this task

> **Note:** By default, the API token generated from the settings page is valid for 180 days and is not associated with a trusted IP address. You can instead generate an API token from the **API Tokens** page and configure a trusted IP address from the list of Microsoft Security Copilot egress IP addresses. For more information about how to configure an API token with trusted IP addresses, see Allow Microsoft Security Copilot egress IP addresses on page 94. For more information about how to rotate an API token, see Rotate Microsoft Security Copilot API tokens on page 95.

Establish communication between a Tanium instance and Microsoft Security Copilot using:

- a URL to a Tanium instance to connect Microsoft Security Copilot to the Tanium instance and configure skills
- a Tanium API token to grant Microsoft Security Copilot permission to query your network using Tanium and gather endpoint data

1. In a browser window, navigate to the Microsoft Security Copilot home page.
2. In the prompt bar at the bottom of the Microsoft Security Copilot home page, click Microsoft Security Copilot plugin .
   The Manage sources modal appears.
3. From the list of plugins, click **Set up** next to the **Tanium** plugin. The Tanium settings modal appears.
4. In a separate browser window, navigate to Tanium Console.
5. From the Main menu, go to **Shared Services** > **Integrations Gallery**, and then click **Microsoft**

©2026 Tanium Inc. All Rights Reserved

Security Copilot.

6. Go to the **Configuration** tab.
   Figure 1. Example Configuration tab in Connect settings
   

7. Click **Tanium Instance URL** Copy to copy the Tanium instance URL to the clipboard.
8. In Security Copilot, paste the **Tanium Instance URL** in the Tanium settings modal.
9. In Tanium Console, click **Generate** to generate an API token and copy the token value to the clipboard. This API token is associated with the user account creating the token, the **Microsoft Security Copilot Operator** persona, contains `Microsoft Security Copilot` in the **Notes** field, and is valid for 180 days from generation.

   Note: You cannot view the token value in Tanium Console. Paste the value in a plaintext editor and save the file in a secure location if you want to record it for future reference.

   Note: Do not use a single token for multiple processes. For example, do not use a single token for a ServiceNow integration and a Splunk integration, or for multiple ServiceNow instances, or for multiple connections from one ServiceNow instance to Tanium Cloudthe Tanium Server. When a token rotates for any process, that token stops working for any other processes that use it.

   Note: You must have the **Microsoft Security Copilot Operator** persona assigned to your user account to generate an API token. Admin users are assigned the persona automatically after they click **Generate**, if their user account does not yet have the persona assigned. Non-admin users must have the persona assigned by an administrator and cannot click **Generate** until the persona is assigned.
10. In Microsoft Security Copilot, paste the API token value in the **Value** field in the Tanium settings modal.
11. To use the Tanium Security Triage Agent with Identity Insights, enter the **Azure Tenant ID**, **Azure Subscription ID**, **Azure Resource Group Name**, and **Azure Sentinel Workspace Name** associated with the Microsoft Sentinel data lake deployment.

©2026 Tanium Inc. All Rights Reserved

12. Click **Save**.

Configure Tanium agents for Microsoft Security Copilot

About this task

You can also download Tanium agents for Microsoft Security Copilot from the Microsoft Security Store and then configure Tanium agents, including generating an API token for using the agent.

> **Note:** The Tanium Security Triage Agent with Identity Insights requires a hybrid Microsoft Entra ID deployment.

> **Note:** For more information about agent configuration, see Microsoft Security Copilot documentation: Manage Security Copilot agents.

1. In a browser window, navigate to the Microsoft Security Store and download and deploy a Tanium agent.
2. Go to a Microsoft store to install an agent.
   - If the agent does not integrate with Microsoft Defender, in a browser window, go to the Microsoft Security Store.
   - If the agent does integrate with Microsoft Defender, such as the Security Health Analyzer Agent, in a browser window, go to the Microsoft Defender Security Store.
3. Enter the agent name in the search field, such as `Tanium Security Health Analyzer Agent` and then press Enter.
4. Click the tile for that agent.
5. Install the agent.
   - In the Microsoft Security Store, click **Get it now**.
   - In the Microsoft Defender Security Store, click **Get agent**.

   The Get solution wizard appears.
6. Select a **Billing subscription**.

©2026 Tanium Inc. All Rights Reserved

7. Select a **Resource group**.
8. Enter a **Resource name**.
9. Click **Choose plan** and select a billing plan.
10. Click **Next**.
11. Select an **Azure subscription**.
12. Select a **Resource group**.
13. Enter a **Resource name**.
14. Click **Next**.
15. Click **Place order**.
16. In a browser window, go to the Microsoft Security Copilot home page.
17. From the Main menu, go to **Agents**.
18. Find the pane associated with the Tanium agent and then click **Set up**.
19. Click **Set up**. The Set up agent modal appears.
20. Click **Sign in** and then authenticate using your Microsoft credentials to grant necessary read permissions to the agent.

    Note: You must allow pop-up windows in your browser.

21. Click **Next**.
22. If you want to automatically populate prompts for an agent, enter a default value. Otherwise, leave the field blank.
23. Click **Finish**.
24. In a separate browser window, navigate to Tanium Console.
25. From the Main menu, go to **Shared Services** > **Integrations Gallery**, and then click the tile associated with the agent, or **Microsoft Security Copilot**.
26. Go to the **Configuration** tab.
    Figure 2. Example Configuration tab in Connect settings

©2026 Tanium Inc. All Rights Reserved



27. Click **Tanium Instance URL** Copy to copy the Tanium instance URL to the clipboard.
28. In Security Copilot, paste the **Tanium Instance URL** in the Agent settings modal.
29. In Tanium Console, click **Generate** to generate an API token and copy the token value to the clipboard. This API token is associated with the user account creating the token, the **Microsoft Security Copilot Operator** persona, contains `Microsoft Security Copilot` in the **Notes** field, and is valid for 180 days from generation.

    Note: You cannot view the token value in Tanium Console. Paste the value in a plaintext editor and save the file in a secure location if you want to record it for future reference.

    Note: Do not use a single token for multiple processes. For example, do not use a single token for a ServiceNow integration and a Splunk integration, or for multiple ServiceNow instances, or for multiple connections from one ServiceNow instance to Tanium Cloudthe Tanium Server. When a token rotates for any process, that token stops working for any other processes that use it.

    Note: You must have the **Microsoft Security Copilot Operator** persona assigned to your user account to generate an API token. Admin users are assigned the persona automatically after they click **Generate**, if their user account does not yet have the persona assigned. Non-admin users must have the persona assigned by an administrator and cannot click **Generate** until the persona is assigned.
30. In Microsoft Security Copilot, paste the API token value in the **Value** field in the agent settings modal.
31. Enter additional information for specific agents.

Tanium Agent	Configuration
Tanium Security Triage Agent with Identity Insights	Enter the **Azure Tenant ID**, **Azure Subscription ID**, **Azure Resource Group Name**, and **Azure Sentinel Workspace Name** associated with the Microsoft Sentinel data lake deployment.

©2026 Tanium Inc. All Rights Reserved

32. Click **Save**.

Using the Tanium API plugin for Microsoft Security Copilot

The Tanium API plugin, in response to a natural language prompt or prompt suggestion to Microsoft Security Copilot, selects an appropriate Tanium skill to evaluate the prompt and return a relevant response.

Use Tanium skill prompts with Microsoft Security Copilot

Use Tanium prompts with Microsoft Security Copilot to prompt for information about hosts on your network. Security Copilot supports natural language prompts and prompt suggestions:

Types of prompts with Microsoft Security Copilot

Prompt type	Description	Notes
natural language prompt	a free-form question or request that uses natural language	Natural language prompts offer a more conversational experience when interacting with Microsoft Security Copilot, and might return more comprehensive responses than prompt suggestions. For more information, see Microsoft Security Copilot documentation: Create your own prompts.
prompt suggestion	an available plugin skill, selected from the list of available system capabilities, and user-provided parameters	Prompt suggestions offer a more structured experience when interacting with Microsoft Security Copilot, and might return less comprehensive responses than natural language prompts. For more information, see Microsoft Security Copilot documentation: Using the prompts library .

Depending on your situation, submitting a natural language prompt might be more efficient than submitting a prompt suggestion.

A well-composed natural language prompt enables an AI model to better provide a relevant response. AI models might match prompt context and specificity, and might respond to a less-focused prompt with sparse or generic information. Issuing additional prompts to improve response quality increases overall computing resources use and decreases efficiency, compared to a single prompt that retrieves relevant information. Use the following best practices to create a natural language prompt:

©2026 Tanium Inc. All Rights Reserved

Best practices for natural language prompts

Natural language prompt attribute	Considerations
Unambiguous language	• Avoid slang terms and metaphors, which might be interpreted in a different way than intended. • Be consistent with words, phrases, and capitalization within a prompt, as AI models might use additional computing resources to evaluate the same term stated in different ways (such as "endpoint" versus "Endpoint", or "endpoint" versus "workstation"). • Use punctuation, such as commas, colons, and periods, to reduce ambiguity within a prompt.
Specific request	• Start the prompt with a clear, defined task that reflects the information that you want. For example, "Return all endpoints that have risks." does not limit endpoint type or specify the risk type. "Return all Windows endpoints that are running unusual processes and require further investigation." specifies which endpoints to focus on, the risk type (unusual running processes), and the goal of conducting an investigation. • Define a persona so that the AI model can tailor the response to a specific audience. For example, specifying a junior security operations center (SOC) member or a SOC lead helps the AI model to emphasize information relevant for that audience. • Provide relevant and detailed context in the prompt. When providing context, avoid negation and instead request an alternative, as an AI model might misinterpret a negated request. For example, instead of submitting "Do not return Windows 11 endpoints," submit "Instead of Windows 11 endpoints, return endpoints running Windows 10 or earlier versions." • Define information you want in the response and the response output format, such as returning information in a table. For example, instead of "Return the affected endpoints," submit "Return the IP address and host name of affected endpoints in a table, sorted in ascending alphabetical order by host name."
Structured format	• Add additional structure, especially if the prompt contains a complex request. For example, if you want to retrieve multiple types of endpoint information from different endpoint types, add lists of requests to your prompt, such as "For Windows endpoints only, return the IPv4 address, MAC address, and host name. For Linux endpoints only, return the IPv4 address, host name, and Linux distribution and version." • Break down a complex end goal into smaller, defined intermediate steps. Instead of "Provide a summary of remediation steps for all endpoints vulnerable to CVE-2014-123456," submit "Summarize the CVE-2014-123456 vulnerability and the effect on endpoints for a junior SOC member. Identify all endpoints on the network that are vulnerable to CVE-2014-123456. Return these endpoints in a table, and also list the remediation steps necessary to patch these endpoints or otherwise remove the vulnerability from these endpoints, and provide

©2026 Tanium Inc. All Rights Reserved

Natural language prompt attribute	Considerations
	relevant detail for a junior SOC member."

Note the following:

- Microsoft charges Microsoft Security Copilot users based on the provisioned Security Compute Units (SCU). For more information, see Microsoft Azure documentation: Microsoft Security Copilot pricing.
- Submitting a prompt and receiving a response might take several seconds or more. As you submit additional prompts in a single session, the time to respond might increase. The Microsoft Security Copilot LLM analyzes all session information, including prior prompts and responses. As a result, creating multiple sessions for different lines of inquiry might save time over a single session containing multiple lines of inquiry.
- Adding specific context to a natural language prompt might improve response accuracy. For example, adding `Using Tanium` to your prompt provides additional context to the Microsoft Security Copilot LLM to select a relevant Tanium Skill. Alternatively, narrowing the scope of a natural language prompt to a specific host on your network might provide a more relevant response for your situation, rather than prompting for all hosts on the network.

For more information about how to submit prompts to Microsoft Security Copilot, see Microsoft Security Copilot documentation: Prompting in Microsoft Security Copilot and Microsoft Security Copilot documentation: Create effective prompts.

TANIUM SKILLS EXAMPLE PROMPTS

The following table provides example natural language prompts related to each Tanium Skill.

> **Note:** Before submitting an example natural language prompt to Microsoft Security Copilot, update any variables and adjust the prompt based on your situation or goal.

©2026 Tanium Inc. All Rights Reserved

Natural language prompts related to each Tanium Skill

Required Tanium solutions	Tanium Skill prompt suggestion	Description	Example natural language prompts
Tanium Core Platform	Get Logged In User	Retrieve the user that is currently logged into an endpoint.	`Using Tanium, return the user currently logged into the endpoint with the hostname <hostname> so that I, a junior security operations center member, can investigate possible unauthorized endpoint use. Return a Tanium Console Question Results URL so that I can view more real-time information for this endpoint. Thank you.`
Tanium Core Platform, sensor-dependent	Get Real-time Data from Endpoints	Retrieve real-time data from endpoints based on a Tanium sensor. For more information about supported sensors, see Get Real-time Data from Endpoints prompt sensor support on page 80 .	`Using Tanium, return the computer name and IP address of endpoints. Display the results in a table, alphabetically sorted by computer name, and return a Tanium Console Question Results URL so that I, a junior security operations center member, can view the real-time list of endpoints. Thank you.`
Asset, SBOM	Count Endpoints Having Package Version	Retrieve the total number of endpoints that have the given software package at a version.	`Using Tanium, return the total number of endpoints that have a given software package <software-name> at version <software-version>, so that I, a junior security operations center member, can start cataloging which computers have the software installed. Display the results in a table, alphabetically sorted by operating system, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
Asset, SBOM	List Endpoints Having Package	Retrieve up to 10 endpoints that have the given software package.	`Using Tanium, return the endpoints with a software package for <software-name> so that I, a junior security operations center member, can start cataloguing which computers might have an out-of-date version. Display the results in a table, alphabetically sorted by host name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
Asset,	List Process	Retrieve the	`Using Tanium, return the SHA-256 hash value and process version for the running process <process-`

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Skill prompt suggestion	Description	Example natural language prompts
SBOM, Threat Response	SHA-256 Hashes and Versions	SHA-256 file hash and version for a given process	`name>, so that I, a junior security operations center member, can find other instances of this process based on the hash value. Thank you.`
Comply	Get Vulnerability Test Results	Return whether an endpoint is vulnerable to a given CVE, and the reason why it is vulnerable.	`Using Tanium, examine whether endpoint <hostname> is vulnerable to <cve-id>, and return the reasons that this endpoint is vulnerable, along with a suggested plan of action to remediate the intrusion tailored to a junior security operations center member. Thank you.`
Comply	List Endpoints Vulnerable To CVE	Retrieve up to 10 endpoints vulnerable to a given CVE ID.	`Using Tanium, return the endpoints vulnerable to <cve-id>, so that I, a junior security operations center member, can remediate the vulnerability on these endpoints. Display the results in a table, sorted alphabetically by host name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
Direct Connect, Threat Response	View Endpoint Processes	Retrieve a URL to the Threat Response Live Connection page for the requested endpoint, which contains a list of running processes. The hostname must match an endpoint hostname exactly.	`Using Tanium, return a Threat Response Live Connection URL for the endpoint with the hostname <hostname>, so that I, a junior security operations center member, can review the running processes and identify potential vulnerabilities. Thank you.`
Incident Response	List Hashes of File	Retrieve the SHA-256 and MD5 file hashes for a given file.	`Using Tanium, retrieve the MD5 and SHA-256 hashes for the file at the file path <full-file-path> so that I, a junior security operations center member, can determine if any malicious file behavior is`

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Skill prompt suggestion	Description	Example natural language prompts
			occurring on the endpoint. Display the results in a table, alphabetically sorted, and return a Tanium Console Question Results URL so that I can view the real-time list. Thank you. Using Tanium, retrieve the MD5 and SHA-256 hashes for the file at the file path <full-file-path> on the endpoint named <hostname> so that I, a junior security operations center member, can determine if any malicious file behavior is occurring on the endpoint. Display the results in a table, alphabetically sorted, and return a Tanium Console Question Results URL so that I can view the real-time list. Thank you.
Incident Response	List Service Module Details	Retrieve running service module information for an endpoint, including name, caption, and image path.	Using Tanium, return information for the service modules running on the endpoint with the hostname <hostname>, so that I, a junior security operations center member, can review the list for unexpected service modules. Display the results in a table, alphabetically sorted by service module name, and return a Tanium Console Question Results URL so that I can view the real-time list of service modules. Thank you.
Incident Response	List Service Process Details	Retrieve running service process information for an endpoint, including name, process ID, and file path.	Using Tanium, return information for the service processes running on the endpoint with the hostname <hostname>, so that I, a junior security operations center member, can review the list for unexpected service processes. Display the results in a table, alphabetically sorted by service process name, and return a Tanium Console Question Results URL so that I can view the real-time list of service processes. Thank you.
Incident Response	List WMI Event Consumers	Retrieve Windows Management Instrumentation (WMI) event	Using Tanium, return the WMI event consumers running on the endpoint with the hostname <hostname> so that I, a junior security operations center member, can ensure only expected event consumers are running, and return a Tanium Console Question Results URL so that I can view the real-time list of event consumers. Thank you.

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Skill prompt suggestion	Description	Example natural language prompts
		consumers running on an endpoint.	
Index	List File Details	Retrieve details for a file by name, including the endpoints on which it is installed, the file path, and file size.	`Using Tanium, return information for the file named <file-name> so that I, a junior security operations center member, can determine if it is running on unintended endpoints. Display the results in a table, alphabetically sorted, and return a Tanium Console Question Results URL so that I can view the real-time list. Thank you.` `Using Tanium, return information for the file named <file-name> installed on the endpoint with the hostname <hostname>, so that I, a junior security operations center member, can determine if it is running on unintended endpoints. Display the results in a table, alphabetically sorted, and return a Tanium Console Question Results URL so that I can view real-time information. Thank you.`
Threat Response	List Child Processes for Process File	Return all child processes running on an endpoint based on a given process file name.	`Using Tanium, list the child processes of <process-name> so that I, a junior security operations center member, can analyze resource usage. Display the results in a table, alphabetically sorted by process name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.` `Using Tanium, list the child processes of <process-name> that are running on the computer with the hostname <hostname>, so that I, a junior security operations center member, can analyze resource usage. Display the results in a table,`

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Skill prompt suggestion	Description	Example natural language prompts
			`alphabetically sorted by process name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
Threat Response	List Endpoints with Process Command	Retrieve up to 10 endpoints running the given command-line command.	`Using Tanium, return the endpoints running the command line command <process-command>, so that I, a junior security operations center member, can ensure this process is not running on unexpected endpoints. Display the results in a table, sorted alphabetically by host name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
Threat Response	List Endpoints with Process Name	Retrieve up to 10 endpoints running the given process.	`Using Tanium, return the endpoints running a process called <process-name>, so that I, a junior security operations center member, can ensure this process is not running on unexpected endpoints. Display the results in a table, sorted alphabetically by host name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
Threat Response	List Endpoints with Process MD5 Hash	Retrieve up to 10 endpoints running the given process matching the provided MD5 hash value.	`Using Tanium, return all endpoints that are running a process with the MD5 hash value <md5-hash-value>, so that I, a junior security operations center member, can ensure this process is not running under a different file name. Display the results in a table, sorted alphabetically by host name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
Threat Response	List File Operations	Retrieve historical file operation information from endpoints, including endpoint name, file path, and the file operation type, such as create or delete.	`Using Tanium, return file operation information for the endpoint named <hostname> running on the file path "<partial-file-path>" over the past <time-frame> so that I, a junior security operations center member, can determine if any malicious file behavior is occuring on the endpoint. Display the results in a table, alphabetically sorted, and return a Tanium Console Question Results URL so that I can view the real-time list. Thank you.`

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Skill prompt suggestion	Description	Example natural language prompts
			Using Tanium, return file operation information for files running on the file path "<partial-file-path>" over the past <time-frame> so that I, a junior security operations center member, can determine if there is any malicious file creation or deletion. Display the results in a table, alphabetically sorted, and return a Tanium Console Question Results URL so that I can view the real-time list. Thank you.
Threat Response	List Processes Connected To IPv4 Address	Retrieve the processes running on an endpoint with the given IPv4 address.	Using Tanium, return the processes running on the endpoint with the IPv4 address <ipv4-address>, so that I, a junior security operations center member, can analyze any potential security intrusions and resource usage. Display the results in a table, sorted alphabetically by process name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.
Threat Response	List Process Ran As User	Retrieve the processes running on an endpoint as a given user.	Using Tanium, return the processes running as the user <user-name>, so that I, a junior security operations center member, can determine whether there are issues with unauthorized access. Display the results in a table, sorted alphabetically by computer name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you. Using Tanium, return the processes running as the user <user-name> on the endpoint with the hostname <hostname>, so that I, a junior security operations center member, can determine whether there are issues with unauthorized access. Display the results in a table, sorted alphabetically by process name, and return a Tanium Console Question

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Skill prompt suggestion	Description	Example natural language prompts
			`Results URL so that I can view the real-time list of endpoints. Thank you.`

GET REAL-TIME DATA FROM ENDPOINTS PROMPT SENSOR SUPPORT

Use the Get Real-time Data from Endpoints prompt to retrieve real-time data from endpoints based on a Tanium sensor. The following example natural language prompts incorporate language similar to a sensor name, providing additional context to Security Copilot to select a related sensor:

- `Using Tanium, return the computer name and IP address of endpoints, so that I, a junior security operations center member, can inventory endpoints on the network. Display the results in a table, alphabetically sorted by computer name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
- `Using Tanium, return the last logged in user for endpoints, so that I, a junior security operations center member, can determine if any user accounts have been displaying suspicious behavior. Display the results in a table, alphabetically sorted by the user name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`
- `Using Tanium, return Microsoft Defender path exclusion information for endpoints, so that I, a junior security operations center member, can verify that configured path exclusions are not too broad. Display the results in a table, alphabetically sorted by computer name, and return a Tanium Console Question Results URL so that I can view the real-time list of endpoints. Thank you.`

©2026 Tanium Inc. All Rights Reserved

GET REAL-TIME DATA FROM ENDPOINTS SUPPORTED SENSORS

The Get Real-time Data from Endpoints prompt supports the following sensors.

> **Note:** You must generate an API token with permission to access the content set to which a sensor belongs to prompt Security Copilot using this sensor.

Sensors supported by the Get Real-time Data from Endpoints prompt

Content set	Sensor
AntiVirus	Microsoft Defender AntiMalware Details
AntiVirus	Microsoft Defender AntiSpyware Details
AntiVirus	Microsoft Defender AntiVirus Details
AntiVirus	Microsoft Defender Computer ID
AntiVirus	Microsoft Defender Extension Exclusions
AntiVirus	Microsoft Defender FullScan Details
AntiVirus	Microsoft Defender Health Details
AntiVirus	Microsoft Defender Installed
AntiVirus	Microsoft Defender IP Address Exclusions
AntiVirus	Microsoft Defender Network Inspection Service Details
AntiVirus	Microsoft Defender On Access Protection Status
AntiVirus	Microsoft Defender Org ID
AntiVirus	Microsoft Defender Path Exclusions
AntiVirus	Microsoft Defender Process Exclusions
AntiVirus	Microsoft Defender QuickScan Details

©2026 Tanium Inc. All Rights Reserved

Content set	Sensor
AntiVirus	Microsoft Defender Real-Time Protection Status
AntiVirus	Microsoft Defender Tamper Protection Status
AntiVirus	Microsoft Defender Threat Details
AntiVirus	Microsoft Defender UI Lockdown Status
Base	Endpoint Fingerprint
Base	Last Reboot
Base	Windows OS Release ID
Certificate Manager	Certificate Manager - SSL Certificate CA Short Name
Certificate Manager	Certificate Manager - SSL Certificate Details
Certificate Manager	Certificate Manager - SSL Certificate Process Details
Certificate Manager	Certificate Manager - SSL Extended Key Usage
Certificate Manager	Certificate Manager - SSL Key Usage
Certificate Manager	Certificate Manager - SSL Server Root Certificate Authority
Certificate Manager	Certificate Manager - Supported SSL/TLS Protocols
Comply Deployment	Comply - Architecture Type
Comply Deployment	Comply - Coverage Status
Comply Reporting	Comply - Compliance Exposure Score
Comply Reporting	Comply - Compliance Findings
Comply Reporting	Comply - Compliance Findings - First Found
Comply Reporting	Comply - Compliance Findings - Last Scan

©2026 Tanium Inc. All Rights Reserved

Content set	Sensor
Comply Reporting	Comply - Compliance Investigation Details
Comply Reporting	Comply - Compliance Percentage
Comply Reporting	Comply - CVE Findings - Last Scan
Comply Reporting	Comply - CVE Investigation Details
Comply Reporting	Comply - Endpoint Scan Status
Comply Reporting	Comply - Has Been Scanned
Comply Reporting	Comply - Is Vulnerable
Comply Reporting	Comply - NMap Scan Results
Comply Reporting	Comply - Open Ports
Comply Reporting	Comply - Oval Findings
Comply Reporting	Comply - Vulnerability Aggregates
Comply Reporting	Comply - Vulnerability Discovery Dates
Core AD Query Content	AD Query - Local Administrators
Core AD Query Content	AD Query - Local Groups
Core AD Query Content	AD Query - Local Users
Core AD Query Content	AD Query - Primary User
Core Content	Active Devices
Core Content	AD Distinguished Name
Core Content	AD Organizational Unit
Core Content	BIOS Vendor

©2026 Tanium Inc. All Rights Reserved

Content set	Sensor
Core Content	BIOS Version
Core Content	BitLocker Details
Core Content	Boot Device
Core Content	Chrome Extensions
Core Content	Cloud Instance Hostname
Core Content	CPU Details
Core Content	Disk Drive Details
Core Content	Driver Details
Core Content	Firefox Extensions
Core Content	Firewall Status
Core Content	Installed Applications
Core Content	Installed HotFixes
Core Content	Installed Pkgs
Core Content	Installed RPMs
Core Content	Installed Store Apps
Core Content	Kernel Modules
Core Content	Kernel Version
Core Content	Last Logged In User
Core Content	Listen Ports
Core Content	Local Account Last Password Change Days Ago

©2026 Tanium Inc. All Rights Reserved

Content set	Sensor
Core Content	Local Administrators
Core Content	Local Administrators Without Groups
Core Content	Local User Login Dates
Core Content	Manufacturer
Core Content	Motherboard Manufacturer
Core Content	Motherboard Name
Core Content	Number of Logged In Users
Core Content	Number Of Users
Core Content	Open Share Details
Core Content	Open Shares
Core Content	Run Once Keys
Core Content	Running Applications
Core Content	Running Processes
Core Content	Running Service
Core Content	Startup Programs
Core Content	Unencrypted Wireless Networks
Core Content	Uptime
Core Content	USB Device
Core Content	User Details
Core Content	User Sessions

©2026 Tanium Inc. All Rights Reserved

Content set	Sensor
Core Content	Windows Security Center Registered Antivirus Software
Core Content	Wireless Network Details
Core Content	Wireless Networks Visible
Discover Content	Open Ports
Enforce Global Objects	Enforce - FileVault Encryption Status
Enforce Global Objects	Enforce - Host Firewall Enabled
Enforce Global Objects	Enforce - Tools Version
Enforce Linux	Enforce - Firewall Rules [Linux]
Enforce Windows	Enforce - BitLocker Encryption Status
Enforce Windows	Enforce - BitLocker Protection Status
Enforce Windows	Enforce - Quarantine Details
Enforce Windows	Enforce - TPM Status
Enforce Windows	Enforce - USB Storage Devices
Impact	Impact - Active User Session SIDs
Impact	Impact - Administrator SIDs
Incident Response	AutoRun Program Details
Incident Response	Elevated Privileges
Incident Response	Loaded Modules Not Matching Whitelist
Incident Response	Running Processes With Filename Mismatch
Incident Response	Running Processes with MD5 Hash

©2026 Tanium Inc. All Rights Reserved

Content set	Sensor
Incident Response	Unsuccessful Elevated Privileges
Reserved	Computer ID
Reserved	Computer Name
Reserved	IP Address
Reserved	Online

Using the Tanium Security Health Analyzer Agent

About this task

Use Tanium agent prompts with Microsoft Security Copilot to analyze endpoint health and receive a detailed response including possible next steps.

> **Note:** The Tanium Security Health Analyzer Agent requires a license for Microsoft Defender as part of a Microsoft 365 subscription.

Tanium Security Health Analyzer Agent details

The Tanium Security Health Analyzer Agent uses the **Get Real-time Data from Endpoints** and **GetIncidentDefenderEntities** skills to retrieve information about endpoints based on host name or Microsoft Defender incident ID.

This agent returns details about:

- Endpoint online status
- Microsoft Defender health status
- Microsoft Defender Antivirus signature age
- Potential next steps

©2026 Tanium Inc. All Rights Reserved

The Tanium Security Health Analyzer Agent requires one or more host names or a Microsoft Defender incident ID. Note the following:

- If you submit a prompt that matches an offline endpoint, the response contains cached data from the last time the endpoint was online.
- If you want to analyze multiple hosts, submit a comma-separated list of host names to analyze multiple endpoints in a single prompt.
- If you submit both host names and a Microsoft Defender incident ID in a prompt, the agent evaluates based on only the host names. Provide either host names or a Microsoft Defender incident ID in a single prompt.

Submit a prompt to the Tanium Security Health Analyzer Agent

TANIUM SECURITY HEALTH ANALYZER AGENT EXAMPLE PROMPT

The following table provides example natural language prompts for the Tanium Security Health Analyzer Agent.



Note: Before submitting an example natural language prompt to Microsoft Security Copilot, replace the example host names or Microsoft Defender incident ID, and adjust the prompt based on your situation or goal.

Natural language prompts for the Tanium Security Health Analyzer Agent

Required Tanium solutions	Tanium Agent	Description	Example natural language prompts
Tanium Core Platform	Tanium Security Health Analyzer Agent	Takes a Microsoft Defender incident ID or one or more host names, analyzes matching online endpoints, and returns a summary of Microsoft Defender installation state, endpoint health, and possible next steps.	`Using the Tanium Security Health Analyzer Agent, evaluate the hosts that match the host names example-hostname, host-example, another-host, and return the analysis results. Thank you.` `Using the Tanium Security Health`

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Agent	Description	Example natural language prompts
		Note: The Tanium Security Health Analyzer Agent requires a license for Microsoft Defender as part of a Microsoft 365 subscription.	`Analyzer Agent, evaluate the Microsoft Defender incident that matches the ID 123456 and return the analysis results. Thank you.`

Pass host names or a Microsoft Defender incident ID directly to the Tanium Security Health Analyzer Agent and run it one time.

1. In a browser window, navigate to the Microsoft Security Copilot home page.
2. From the Main menu, go to **Agents**.
3. In the Tanium Security Health Analyzer Agent pane, click **Go to agent**.
4. Click **Run** > **One time**.
5. Click **Optional fields**.
6. Enter **Host names** or the **Defender Incident ID** and then click **Submit**.
7. In the Activity pane, select a run to view run details.
8. From the run details, click **View activity** to view a graphical map of agent evaluation, including child skills.

Using the Tanium Security Triage Agent

Use Tanium agent prompts with Microsoft Security Copilot to analyze Threat Response alerts and receive a detailed response including possible next steps.

Tanium Security Triage Agent details

The Tanium Security Triage Agent uses the **Fetch Threat Alerts** skill to retrieve information about an alert matching the GUID, and the **Get Direct Connect Process Tree** and **Get Direct Connect Process**

©2026 Tanium Inc. All Rights Reserved

Events skills to establish a direct connection with an endpoint to retrieve process event and artifact information.

This agent returns an initial assessment of the alert, a summary of the analysis, process artifact information, and potential next steps to take, which might include a link to Tanium Console to establish a direct connection with the endpoint.

Submit a prompt to the Tanium Security Triage Agent

The Tanium Security Triage Agent requires a Threat Response alert GUID.

OBTAIN A THREAT RESPONSE ALERT GUID

About this task

To obtain a Threat Response alert GUID, you can either export the alert or view the alert details. With this alert GUID, you can use a Tanium agent to evaluate the Threat Response alert that matches the GUID.

> **Note:** Ensure that the alert GUID is associated with an active alert. If you submit a Tanium agent prompt with an alert GUID that is associated with a resolved or deleted alert, the response returns an error.

1. In a browser window, navigate to Tanium Console.
2. From the Main menu, go to **Modules** > **Threat Response** > **Alerts**.
3. You have the following options:
   - If the GUID column does not appear, click Customize Columns and then select **GUID**. Click Options and then click Copy cell value for an alert GUID to copy the value to the clipboard.
   - Click Advanced Details to view more information for an alert and then click the **GUID** to copy the value to the clipboard. For information on managing Threat Response alerts, see Tanium Threat Response User Guide: Managing Threat Response alerts.
   - Select an alert. Click **Actions** > **Export to CSV** to export a CSV file with the alert GUID.

©2026 Tanium Inc. All Rights Reserved

For information on exporting Threat Response alerts, see Tanium Threat Response User Guide: Export alerts.

TANIUM SECURITY TRIAGE AGENT EXAMPLE PROMPT

The following table provides an example natural language prompt for the Security Triage Agent.

> **Note:** Before submitting an example natural language prompt to Microsoft Security Copilot, replace the example alert GUID with an active alert GUID, and adjust the prompt based on your situation or goal.

Natural language prompt for the Tanium Security Triage Agent

Required Tanium solutions	Tanium Agent	Description	Example natural language prompts
Direct Connect, Threat Response	Tanium Security Triage Agent	Takes an alert from Tanium Threat Response, analyzes it, calls additional subagents to return information, and returns a summary.	`Using the Tanium Security Triage Agent, evaluate analyze the alert GUID 00000000-0000-0000-1234-567890abcdef and return the analysis results. Thank you.`

PASS AN ALERT GUID DIRECTLY TO AN AGENT

About this task

Pass an alert GUID directly to the Security Triage Agent and run it one time.

1. In a browser window, navigate to the Microsoft Security Copilot home page.
2. From the Main menu, go to **Agents**.
3. In the Tanium Security Triage Agent pane, click **Go to agent**.
4. Click **Run** > **One time**.
5. Enter the **Threat Response Alert GUID** and then click **Submit**.
6. In the Activity pane, select a run to view run details.

©2026 Tanium Inc. All Rights Reserved

7. From the run details, click **View activity** to view a graphical map of agent evaluation, including child skills and child agents.

Using the Tanium Security Triage Agent with Identity Insights

Use Tanium agent prompts with Microsoft Security Copilot to analyze Threat Response alerts and receive a detailed response including possible next steps.

Tanium Security Triage Agent with Identity Insights details

The Tanium Security Triage Agent with Identity Insights uses the **Fetch Threat Alerts** skill to retrieve information about an alert matching the GUID, the **Get Direct Connect Process Tree** and **Get Direct Connect Process Events** skills to establish a direct connection with an endpoint to retrieve process event and artifact information, and the **Get Entra User Job Title** skill to retrieve the job title associated with a user account from a hybrid Entra ID environment.

This agent returns an initial assessment of the alert, a summary of the analysis, process artifact information, and potential next steps to take, which might include a link to Tanium Console to establish a direct connection with the endpoint.

Submit a prompt to the Tanium Security Triage Agent with Identity Insights

About this task

The Tanium Security Triage Agent with Identity Insights requires a Threat Response alert GUID.

OBTAIN A THREAT RESPONSE ALERT GUID

To obtain a Threat Response alert GUID, you can either export the alert or view the alert details. With this alert GUID, you can use a Tanium agent to evaluate the Threat Response alert that matches the GUID.

> **Note:** Ensure that the alert GUID is associated with an active alert. If you submit a Tanium agent prompt with an alert GUID that is associated with a resolved or deleted alert, the response returns an error.

©2026 Tanium Inc. All Rights Reserved

1. In a browser window, navigate to Tanium Console.
2. From the Main menu, go to **Modules** > **Threat Response** > **Alerts**.
3. You have the following options:
    - If the GUID column does not appear, click Customize Columns and then select **GUID**. Click Options and then click Copy cell value for an alert GUID to copy the value to the clipboard.
    - Click Advanced Details to view more information for an alert and then click the **GUID** to copy the value to the clipboard. For information on managing Threat Response alerts, see Tanium Threat Response User Guide: Managing Threat Response alerts.
    - Select an alert. Click **Actions** > **Export to CSV** to export a CSV file with the alert GUID. For information on exporting Threat Response alerts, see Tanium Threat Response User Guide: Export alerts.

TANIUM SECURITY TRIAGE AGENT WITH IDENTITY INSIGHTS EXAMPLE PROMPT

The following table provides an example natural language prompt for the Tanium Security Triage Agent with Identity Insights.

> **Note:** Before submitting an example natural language prompt to Microsoft Security Copilot, replace the example alert GUID with an active alert GUID, and adjust the prompt based on your situation or goal.

Natural language promptfor the Tanium Security Triage Agent with Identity Insights

Required Tanium solutions	Tanium Agent	Description	Example natural language prompt
Direct Connect, Threat Response	Tanium Security Triage Agent	Takes an alert from Tanium Threat Response, analyzes it, calls additional subagents to return information, associates an Entra ID job title with the assessment, and returns a	`Using the Tanium Security Triage Agent with Identity Insights, evaluate analyze the alert GUID 00000000-0000-0000-1234-567890abcdef`

©2026 Tanium Inc. All Rights Reserved

Required Tanium solutions	Tanium Agent	Description	Example natural language prompt

	with Identity Insights	summary.
		
		Note: The Tanium Security Triage Agent with Identity Insights requires a subscription to Microsoft Security Copilot, a hybrid Microsoft Entra ID environment, and a Microsoft Sentinel data lake tier subscription.
			`and return the analysis results.`
			
			`Thank you.`

PASS AN ALERT GUID DIRECTLY TO AN AGENT

About this task

Pass an alert GUID directly to the Security Triage Agent with Identity Insights and run it one time.

1. In a browser window, navigate to the Microsoft Security Copilot home page.
2. From the Main menu, go to **Agents**.
3. In the Tanium Security Triage Agent with Identity Insights pane, click **Go to agent**.
4. Click **Run** > **One time**.
5. Enter the **Threat Response Alert GUID** and then click **Submit**.
6. In the Activity pane, select a run to view run details.
7. From the run details, click **View activity** to view a graphical map of agent evaluation, including child skills and child agents.

Troubleshooting the Microsoft Security Copilot integration

Review troubleshooting tasks for common issues.

Allow Microsoft Security Copilot egress IP addresses

©2026 Tanium Inc. All Rights Reserved

Important: Contact Microsoft to confirm the correct egress IP address for your geographical region. These IP addresses are subject to change.

Depending on your geographical region, Microsoft Security Copilot uses one of several IP addresses for communication with the Tanium instance. Add the appropriate IP address to your network allow list to ensure inbound communication from Microsoft Security Copilot to your network. For more information about egress IP addresses, see Microsoft Security documentation: Microsoft Security Copilot egress IPs.

You can also generate an API token associated with a trusted IP address that corresponds to an Azure geographical region and configure Microsoft Security Copilot to use that API token. For more information about how to create an API token, see Tanium Console User Guide: Create an API token.

Rotate Microsoft Security Copilot API tokens

API tokens generated for the Microsoft Security Copilot integration are valid for 180 days from generation, associated with the user account creating the API token and the **Microsoft Security Copilot Operator** persona, and contain **Microsoft Security Copilot** in the **Notes** field. To rotate an API token:

- Administrator users can rotate their existing API token from the **API Tokens** page, using the original token string. For more information about how to rotate an API token, see Tanium Console User Guide: Rotate an API token.
- Non-administrator users can contact an administrator to revoke the existing API token from the **API Tokens** page. The non-administrator users can then generate a new API token. For more information about how to revoke an API token, see Tanium Console User Guide: Revoke an API token.

Review Microsoft Security Copilot-related API token audit logging


About this task

Review API token audit logging on a periodic basis to ensure that traffic using Microsoft Security Copilot-related API tokens is originating from trusted sources, such as a Microsoft egress IP address. You can configure a Connect connection using the **Tanium Audit Source** source, with a SIEM or other logging analysis solution as the destination. After the connection run finishes, filter the log entries for Security Copilot-related API token entries using a regular expression, such as

©2026 Tanium Inc. All Rights Reserved

`"mod_persona":{"id":[0-9]+, ?"name":"Microsoft Security Copilot Operator"}`.

1. From the Main menu, go to **Modules** > **Connect** > **Connections**.
2. Click **Create Connection**.
3. Enter a destination **Name**.
4. Select the **Tanium Audit Source** source. Then select **API Tokens Audit**.
5. Select a **Destination** and configure destination settings.



6. Optionally, in the **Schedule** section, select **Enable Schedule** and configure a schedule for connection runs.
7. Click **Save**.

Next steps

For more information about how to create a Connect connection to a SIEM destination, see Tanium Connect User Guide: Configuring Socket (SIEM) destinations.

Review Microsoft Security Copilot-related questions in Tanium

If Microsoft Security Copilot selects the Tanium API Plugin for Microsoft Security Copilot to evaluate a natural language prompt or prompt suggestion, it uses the configured API token to submit questions in Tanium and generate a response. Responses might include a URL to question results in Tanium Console. You can view the question history and filter results based on the user associated with the API token to review the questions Microsoft Security Copilot issues, and to confirm communication between Microsoft Security Copilot and Tanium. For more information about how to view question history, see Tanium Interact User Guide: View question history.

©2026 Tanium Inc. All Rights Reserved

Improve selection of Tanium Skills

About this task

To respond to a natural language prompt, Microsoft Security Copilot analyzes available prompt and session context, and selects a relevant plugin and skill. If you want Microsoft Security Copilot to select Tanium Skills in response to natural language prompts, and Microsoft Security Copilot instead repeatedly selects non-Tanium Skills, you have the following options:

- Add specific context to a natural language prompt. For example, adding `Using Tanium` to your prompt provides additional context to the Microsoft Security Copilot LLM to select a relevant Tanium Skill.
- Submit a prompt suggestion for a specific Tanium Skill.
- Submit additional Tanium Skill-related prompts in a session.
- Provide response feedback to Microsoft to help improve future versions of Microsoft Security Copilot.

If Microsoft Security Copilot continues to select non-Tanium Skills, you can disable other Microsoft and non-Microsoft plugins, improving the possibility that Microsoft Security Copilot selects a Tanium Skill. For more information, see Microsoft Security Copilot documentation: Manage plugins in Microsoft Security Copilot.

Note: Disabling the Public web plugin, which retrieves internet content, might decrease overall response quality.

1. From the Microsoft Security Copilot home page, click Security Copilot plugin. The Manage plugins modal appears.
2. Select the toggle for each enabled non-Tanium plugin to turn off the plugin.
3. Close the modal.

©2026 Tanium Inc. All Rights Reserved

Managing the Microsoft Teams integration with Jump Gate

Important:

To use the Tanium integration with Microsoft Teams, you must be:

- a Microsoft Teams subscriber
- a Tanium on-premises customer

For more information, see Microsoft Teams: Find the right Microsoft Teams for your business.

The Tanium integration with Microsoft Teams enables notifications from Tanium Jump Gate to a Microsoft Teams public channel or chat, based on supported Tanium functionality.

Requirements

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium™ Core Platform servers
- Tanium™ Client: No client requirements.

Required dependencies

The Microsoft Teams integration has the following required dependencies:

- Tanium Partner Integration

©2026 Tanium Inc. All Rights Reserved

Feature-specific dependencies

Note: The Microsoft Teams integration does not appear unless you install Tanium Jump Gate.

- Tanium Jump Gate to send notifications to Microsoft Teams when a request is ready for approval

User role and persona requirements

The following tables list the role permissions required to configure the Microsoft Teams integration. To review a summary of the predefined roles, see User role and persona requirements on page 99.

For more information about role permissions and associated content sets, see Tanium Console User Guide: RBAC overview.

Microsoft Teams user role permissions

Permission	Integration Operator - Microsoft Teams [1]	Integration Viewer - Microsoft Teams [1]
Partner Integration View the Integrations Gallery workbench	✓ SHOW	✓ SHOW
Partner Integration Api Use the Integrations Gallery API	✓ EXECUTE	✓ EXECUTE
Partner Integration Connection Confirm connection with an integration	✓ VERIFY	✓ VERIFY
Partner Integration Credentials View and configure the Integrations Gallery credentials	✓ READ WRITE	✓ READ
Partner Integration Gallery View the Integrations Gallery	✓ READ	✓ READ

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Operator - Microsoft Teams [1]	Integration Viewer - Microsoft Teams [1]
Partner Integration Gallery Microsoft Teams View the Microsoft Teams settings in Integrations Gallery	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View reporting metrics in Integrations Gallery	✓ READ	✓ READ

[1] This role provides module permissions for Tanium Reporting. You can view which Reporting permissions are granted to this role in Tanium Console. For more information, see Tanium Reporting User Guide: User role requirements .

Provided Microsoft Teams administration and platform content permissions

Permission	Permission Type	Integration Operator - Microsoft Teams	Integration Viewer - Microsoft Teams
Action Group	Administration	✓ READ	✓ READ
Filter Group	Platform	✓ READ	✓ READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

View the Details page

About this task

The **Details** page for the Microsoft Teams integration shows the following information:

- **Service Enablement** toggle
- **Configuration** status
- **Usage** reports

©2026 Tanium Inc. All Rights Reserved

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Teams for Jump Gate**.

View the Configuration page

About this task

The **Configuration** page for the Microsoft Teams integration shows the following information:

- **Integration Instance Configurations**
- **Role Assignment**: For more information, see User role and persona requirements on page 99.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Teams for Jump Gate**.
3. Click **Configuration**.

View the About page

About this task

The **About** page for the Microsoft Teams integration shows the following information:

- **Integrate with Jump Gate**
- **Requirements**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Teams for Jump Gate**.
3. Click **About**.

©2026 Tanium Inc. All Rights Reserved

Configure Microsoft Teams integration with Tanium Jump Gate

About this task

To configure the Microsoft Teams integration with Tanium Jump Gate:

1. Configure a Microsoft Teams webhook for a public channel or chat. Copy the HTTP POST URL. Configure a Microsoft Teams configuration in Tanium Console to pass information from Tanium to Microsoft Teams. For more information, see Create a Microsoft Teams configuration on page 102.
2. Configure a Jump Gate access policy and enable external notifications. For more information, see Tanium Cloud User Guide: Configuring network egress for Tanium Cloud.

Result

Note: To allow Microsoft Teams notifications from Tanium Core Platform, configure a network egress allow list rule to allow outbound traffic from Tanium to Microsoft Teams for the HTTP POST URL over port 443/TCP.

Enable the Microsoft Teams integration

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Teams for Jump Gate**.
3. Click **Enable** and then confirm your selection.

Create a Microsoft Teams configuration

About this task

Note: Use the **Integration Operator - Microsoft Teams** system role to configure the Microsoft Teams instance.

In Microsoft Teams, configure a Microsoft Teams webhook for a public channel or chat to send notifications to the channel or chat name using the webhook HTTP POST URL. Then, in Tanium, create a Microsoft Teams configuration for each Microsoft Teams public channel or chat to which you

©2026 Tanium Inc. All Rights Reserved

want to send notifications. For more information about creating a Microsoft Teams webhook, see Microsoft Teams documentation: Create incoming webhooks with Workflows for Microsoft Teams.

1. In Microsoft Teams, right-click a public channel name or user name and select **Workflows**.
2. Select **Send webhook alerts to a channel** or **Send webhook alerts to a chat**.
3. Enter a workflow **Name** and confirm that there is a valid **Connection**.
4. Click **Next**.
5. Confirm the details and then click **Add workflow**.
6. Copy the webhook URL value and then paste this in a plain text editor.
7. Click **Done**.
8. In Tanium Console, from the Main menu, go to **Shared Services** > **Integrations Gallery**.
9. In the **Integrations** section, click **Microsoft Teams for Jump Gate**.
10. Click **Create Microsoft Teams configuration**.
11. Enter a Microsoft Teams instance **Name**.
12. Copy the webhook URL value from the plain text editor and paste this value in **Microsoft Teams Webhook URL**.
13. Click **Create**.

Edit a Microsoft Teams instance

About this task

Edit a Microsoft Teams instance to update the display **Name** and **Microsoft Teams Webhook URL**.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Teams for Jump Gate** and then click **Configuration**.
3. Click Edit Instance next to a Microsoft Teams instance.
4. Configure the settings.
5. Click **Save**.

©2026 Tanium Inc. All Rights Reserved

Delete a Microsoft Teams instance

About this task

Deleting a Microsoft Teams instance disables sending future notifications from Tanium to Microsoft Teams.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Teams for Jump Gate** and then click **Configuration**.
3. Click Delete Instance  for the Microsoft Teams instance that you want to delete.

Troubleshoot issues

If the Microsoft Teams integration is not performing as expected, you might need to troubleshoot issues or change settings.

Cannot establish a connection between Tanium and Microsoft Teams

Ensure that a network egress allow list rule allows outbound traffic from Tanium to Microsoft Teams for the HTTP POST URL over port 443/TCP.

The Network Egress Allow List was not updated

After you save the Microsoft Teams configuration, a warning states that the Network Egress Allow List was not updated.

©2026 Tanium Inc. All Rights Reserved

Managing the ScreenMeet Screen Sharing integration

With the ScreenMeet Screen Sharing integration, you can easily manage and have complete control of your end-user devices. Secure remote takeover gives you quick access to your endpoints. Agents and employees work together over video, voice, screen share, and mobile camera share.



Important: To enable this functionality, you must purchase the ScreenMeet offering. With the ScreenMeet offering provided through Tanium, you must initiate all interactions with ScreenMeet through Tanium Console. Contact Tanium for details.

Requirements

- Tanium Screen Sharing is required.
- Obtain Screen Sharing per-operator licenses based on the number of Tanium Console operators you expect to establish screen sharing sessions.
    - A per-operator license is allocated to each Tanium Console operator establishing a screen sharing session or accessing the ScreenMeet console from Tanium Console. Each Tanium Console operator can create unlimited concurrent screen sharing sessions.
    - The license allocation lasts for 30 days and counts as an active operator license. The 30-day license allocation restarts each time that a Tanium Console operator establishes a screen sharing session or opens the ScreenMeet console.
    - If the active operator license count exceeds your total per-seat license count, additional Tanium console operators cannot establish a screen sharing session.
- Set up screen sharing users in Tanium. For more information about permissions provided by these roles, see Screen Sharing user role permissions on page 108. For more information about configuring permissions to establish unattended screen sharing sessions, see

©2026 Tanium Inc. All Rights Reserved

[Configure permissions to establish unattended screen sharing sessions on page 117](#).

- **Integration Admin - ScreenMeet**: With this role, a user can change settings, features and policies; access data; and join active sessions created by active users. A user assigned this role in Tanium is automatically assigned the **ScreenMeet Admin** role in ScreenMeet and can access the ScreenMeet console to configure ScreenMeet settings for the organization using a magic link accessed from the **Details** page of the **ScreenMeet Screen Sharing** integration in Integrations Gallery. For more information, see [Configure ScreenMeet settings on page 129](#).

- **Integration Viewer - ScreenMeet**: With this role, a user can view the ScreenMeet integration in Integrations Gallery

- **Screen Sharing Agent**: With this role, a user can start sharing sessions and use standard ScreenMeet features. A user assigned this role in Tanium is automatically assigned the **ScreenMeet Agent** role in ScreenMeet. This role includes the **Screen Sharing Console** permission, which allows access to the ScreenMeet console without the ability to modify organizational settings using a magic link accessed from the Direct Connect settings.

- **Screen Sharing Support Session Unattended Execute** permission: Establish unattended sessions with Windows endpoints that do not require endpoint user permission. After the user ends the unattended session, the endpoint locks by default. This permission is not assigned to any default role.

- **Screen Sharing Support Session Disable Autolock Execute** permission: Disable automatic endpoint locking after ending an unattended session that the user established. This permission requires the **Screen Sharing Support Session Unattended Execute** permission to establish unattended sessions. This permission is not assigned to any default role.

  Tip: Use a least-privilege model for your screen sharing users.

- Verify endpoint operating systems. For more information, see [Screen sharing operating systems on page 107](#).

- Verify network requirements.

©2026 Tanium Inc. All Rights Reserved

- Configure the host and network security requirements. For more information, see Host and network security requirements on page 108.
- Allow ScreenMeet application traffic through port 443/TCP and 443/UDP. ScreenMeet application traffic goes through TLS-encrypted connections.
- Ensure that the ScreenMeet security requirements are configured. For more information, see ScreenMeet Documentation: Security.

Managing the ScreenMeet Screen Sharing integration

Screen Sharing OS support

The following endpoint operating systems are supported for screen sharing through Tanium. For more information about the operating systems that ScreenMeet supports, see ScreenMeet Documentation: Requirements.

Note: The first time a Tanium Console operator establishes a screen sharing session with a macOS endpoint, the endpoint user must select **ScreenMeetSupport** in the **Screen Recording** and **Accessibility** permissions in **System Settings**, then click **Later** when prompted. For more information, see ScreenMeet Documentation: Connecting to Mac devices.

Supported operating systems for Screen Sharing

Operating System	Version	Notes
Windows	• Windows 11	Windows operating systems also require .NET Framework 4.8 or later. Windows operating systems support attended and unattended screen sharing sessions.
Windows Server	• Windows Server 2025 • Windows Server 2022	
macOS	• 15 or later	macOS operating systems support only attended screen sharing sessions.

©2026 Tanium Inc. All Rights Reserved

PORTS FOR SCREEN SHARING COMMUNICATION

Screen Sharing requires the following port.

Ports for Screen Sharing communication

Source	Destination	Port	Protocol	Purpose
Tanium Module Server	*.cloud.tanium.com	443	TCP	Required for the Tanium Module Server to connect to Tanium™ Account for provisioning an on-premises configuration

Network requirements

The endpoints in your environment require access to certain URLs to establish screen sharing sessions. If security software is deployed in the environment to monitor and block unknown URLs, your security administrator might need to allow the hosts and IP addresses listed at ScreenMeet Documentation: Firewall configuration / whitelisting and ScreenMeet Documentation: Egress IP Addresses, and allow the following URL.

Note: Allowing this URL is not required for Direct Connect.

Third-party URL required for Screen Sharing

URL	Source	Port	Protocol	Description
*.screenmeet.com	ScreenMeet client	443	TCP / UDP	Required for endpoints to establish screen sharing connections

Note: For the best results, allow traffic from the preceding URL to bypass proxy servers if you deployed such servers in your network. Screen sharing traffic that passes through proxy servers negatively impacts performance. For more information, see ScreenMeet Documentation: ScreenMeet Enterprise Deployment Guide.

User role requirements

©2026 Tanium Inc. All Rights Reserved

Predefined roles grant the following permissions, which are required to use ScreenMeet Screen Sharing integration functionality:

- Table 25. ScreenMeet Screen Sharing solution permissions on page 109
- ScreenMeet Screen Sharing administration, platform content, and global permissions on page 112: The solution permissions automatically provide some of these permissions.

Some ScreenMeet Screen Sharing solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to ScreenMeet Screen Sharing. If you create custom roles for ScreenMeet Screen Sharing users, be sure to assign all the solution permissions and content set permissions that are required for ScreenMeet Screen Sharing functionality. If you are not sure which permissions are required for a custom role, view the permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)
- Provided role permissions
- View effective role permissions
- Configure a custom role

ScreenMeet Screen Sharing solution permissions

Permission	Integration Admin - ScreenMeet [1]	Integration Viewer - ScreenMeet [1]	Screen Sharing Agent [1]
Partner Integration View the Integrations Gallery workbench	✓ SHOW	✓ SHOW	✓ SHOW
Partner Integration Api Use the Integrations Gallery API	✓ EXECUTE	✓ EXECUTE	✓ EXECUTE
Partner Integration Credentials View and configure the Integrations Gallery credentials	✓ READ	✗	✗

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Admin - ScreenMeet [1]	Integration Viewer - ScreenMeet [1]	Screen Sharing Agent [1]
	WRITE DELETE		
Partner Integration Gallery View and configure the Integrations Gallery	✓ READ	✓ READ	✓ READ
Partner Integration Gallery Screenmeet View and configure the ScreenMeet integration	✓ READ WRITE	✓ READ	✓ READ
Partner Integration Reporting Metrics View reporting metrics in Integrations Gallery	✓ READ	✓ READ	✓ READ
Screen Sharing Api Connect to Screen Sharing API	✓ EXECUTE	✓ EXECUTE	✓ EXECUTE
Screen Sharing Audit Event Log View or create event log for auditing purposes	✓ READ WRITE	✗	✗
Screen Sharing Config For internal purposes only	✓ READ WRITE	✓ READ	✓ READ
Screen Sharing Console Get magic URL for accessing ScreenMeet console	✓ EXECUTE	✗	✓ EXECUTE
Screen Sharing Console Admin Get magic URL for accessing ScreenMeet console and organizational settings	✓ EXECUTE	✗	✗

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Admin - ScreenMeet [1]	Integration Viewer - ScreenMeet [1]	Screen Sharing Agent [1]
Screen Sharing Feed Integration User Interact with notifications from Tanium Feed	✓ ACCOUNT	✗	✗
Screen Sharing Gallery View the ScreenMeet content in Integrations Gallery	✓ READ	✓ READ	✗
Screen Sharing Integration Configure ScreenMeet in Integrations Gallery	✓ ADMIN	✓ VIEWER	✗
Screen Sharing Platform Integration User Interact with the platform	✓ ACCOUNT	✗	✓ ACCOUNT
Screen Sharing Product Options Retrieve ScreenMeet product options values: Show recording option (provided by **Screen Sharing Support Session** Write)	✓ READ	✗	✓ READ
Screen Sharing Provisioning Otp Set provisioning information in one-time passcode	✓ WRITE	✗	✗
Screen Sharing Reporting Metrics Get reporting metrics	✓ READ	✓ READ	✓ READ
Screen Sharing Settings Configure screen sharing settings	✓ READ WRITE	✓ READ	✓ READ
Screen Sharing Support Session Start a screen sharing session on a remote endpoint, requiring endpoint user permission	✓ READ WRITE EXECUTE	✓ READ	✓ READ WRITE EXECUTE

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Admin - ScreenMeet [1]	Integration Viewer - ScreenMeet [1]	Screen Sharing Agent [1]
	DELETE		DELETE
Screen Sharing Support Session All Join any screen sharing session, even if another user started the session	✓ READ EXECUTE DELETE	✗	✗
Screen Sharing Support Session Options [2] Set screen sharing options that do not have corresponding settings available in the ScreenMeet console	✓ READ WRITE	✓ READ	✓ READ
Screen Sharing Tds Integration User Interact with data from Tanium Data Service	✓ ACCOUNT	✓ ACCOUNT	✓ ACCOUNT

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

[2] This permission does not currently have any effect on the available settings in the Screen Sharing workbench. It is provided in support of internal APIs used by the Screen Sharing service.

ScreenMeet Screen Sharing administration and platform content permissions

Permission	Permission Type	Integration Admin - ScreenMeet	Integration Viewer - ScreenMeet	Screen Sharing Agent
Action Group	Administration	✓ READ	✓ READ	✓ READ
Action	Platform	✓ READ WRITE	✗	✓ WRITE

©2026 Tanium Inc. All Rights Reserved

Permission	Permission Type	Integration Admin - ScreenMeet	Integration Viewer - ScreenMeet	Screen Sharing Agent
Filter Group	Platform	READ	READ	READ
Own Action	Platform	READ		READ
Package	Platform	READ	READ	READ
Plugin	Platform	READ EXECUTE	READ EXECUTE	READ EXECUTE
Sensor	Platform	READ	READ	READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

View the Details page

About this task

The **Details** page for the ScreenMeet Screen Sharing integration shows the following information:

- **Service Enablement** toggle
- **Account Status**
- **Licenses** count
- **Licenses in Use** count
- **License Alert Threshold** percentage

©2026 Tanium Inc. All Rights Reserved

- **Access** link
- **Usage** reports
    - **Sessions**
    - **License Usage**
- **Screen Sharing Sessions** list
- **License Usage** list

If AI summaries are enabled in ScreenMeet, the **AI Summary** column in the **Screen Sharing Sessions** list shows **Not Available** until ScreenMeet generates an AI summary of the session. When a summary is available, click **View Summary** to view the summary of the actions taken during the session and the likely resolution.

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.

View the Configuration page

About this task

The **Configuration** page for the ScreenMeet Screen Sharing integration shows the following information:

- **Role Assignment**: For more information, see User role requirements on page 108.
- **License Usage** with **Users** list and **Alert Threshold** setting

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.
3. Click **Configuration**.

©2026 Tanium Inc. All Rights Reserved

View the Tanium Content page

About this task

The **Tanium Content** page for the ScreenMeet Screen Sharing integration shows the following information:

- **Reports**
    - **Endpoints Ready for Screen Sharing**

To view the **Tanium Content** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.
3. Click **Tanium Content**.

View the Support page

About this task

The **Support** page for the ScreenMeet Screen Sharing integration shows the following information:

- **Create Package** button to create a troubleshooting package for support requests

To view the **Support** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.
3. Click **Support**.

View the About page

About this task

The **About** page for the ScreenMeet Screen Sharing integration shows the following information:

©2026 Tanium Inc. All Rights Reserved

- **Real-Time Support** video
- **Collaborate**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.
3. Click **About**.

Enable the integration

About this task

To get started, you must enable the Screen Sharing integration.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.
3. Click **Enable** and then confirm your selection.

Integrate with ServiceNow

About this task

Integrate Screen Sharing with your ServiceNow instance to update ServiceNow tickets with audit logs from a related screen sharing session. With this integration, you have an additional option when opening screen sharing sessions: **Send audit log to ServiceNow**. If you select this option, you can add the ServiceNow Ticket ID that is associated with the screen sharing session.

If ScreenMeet generates an AI summary of the session, the summary is also added to the associated ServiceNow ticket.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**. Click Settings and then click **Screen Sharing**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.
3. Click **Configuration**.

©2026 Tanium Inc. All Rights Reserved

4. In the **ServiceNow Configuration** section, provide the **Host URL**, **Username** and **Password** for your ServiceNow instance. Click **Save**.

> **Note:** The ITIL role in ServiceNow is required to integrate activities from ServiceNow.

For the steps to open a screen sharing session, see Open an endpoint screen sharing session on page 119. After you close a screen sharing session where you sent the audit log to ServiceNow, you can check the status of the sync on the **Audit Log** page in Direct Connect. From the Main menu, go to **Shared Services** > **Integrations Gallery> Audit Log** > **Screen Sharing Sessions**. Audit logs can have the following sync statuses:

Status	Meaning
Pending	The session is queued for session log syncing.
In Progress	Session log syncing is in progress.
Complete	The session log was successfully synced with ServiceNow.
Error	The session log failed to sync with ServiceNow.

Configure personas to establish unattended screen sharing sessions

About this task

The ability to establish unprompted (unattended) screen sharing sessions is intentionally limited by default to only Tanium administrators to prevent misuse. The default **Integration Admin - ScreenMeet**, **Screen Sharing Agent**, and **Integration Viewer - ScreenMeet** user roles do not have this permission. In addition, Tanium Console operators that establish an unattended screen sharing session with an endpoint and then close the session lock the endpoint by default.

You can configure a custom role and persona with permissions to establish unattended screen sharing sessions with an endpoint, and leave the endpoint unlocked after the unattended screen sharing session is closed. You can restrict the persona to a given computer group, and assign the persona to only certain Tanium Console operators.

For more information about creating a custom role, see Tanium Console User Guide: Configure a

©2026 Tanium Inc. All Rights Reserved

custom role. For more information about creating a persona, see Tanium Console User Guide: Create a persona.

1. From the Main menu, go to **Administration** > **Permissions** > **Roles** and click **New Role**.
2. Specify a **Role Name**, such as `Screen Sharing Unattended Role`.
3. Set the **Permission Type** to **Allow**.
4. Select the **Screen Sharing Support Session Unattended Execute** permission to allow users to establish unattended screen sharing sessions.
5. If you want a Tanium Console operator to have the option to leave an endpoint unlocked after closing an unattended screen sharing session, select **Screen Sharing Support Session Disable Autolock Execute**.
6. Click **Save**.
7. From the Main menu, go to **Administration > Permissions > Personas** and click **New Persona**.
8. Specify a persona **Name**, such as `Screen Sharing Unattended Persona`.
9. Click **Manage Roles**.
10. Select the following roles:
    - **Interact Basic User** for Interact access
    - **Screen Sharing Agent** for screen sharing access
    - **Screen Sharing Unattended Role** (or the name of the role you created) for unattended screen sharing session options
11. Click **Apply**.
    The Permissions table displays the union of permissions from these roles, including **Screen Sharing Support Session Unattended Execute** and, if you configured it, **Screen Sharing Support Session Disable Autolock Execute**.
12. Expand the **Computer Groups** section and click **Manage Computer Groups**.
13. Select the computer groups that contain the endpoints to which you want to establish unattended screen sharing sessions, then click **Select**.
14. If you configured a user group to contain your Tanium Console operators that will establish

©2026 Tanium Inc. All Rights Reserved

screen sharing sessions with endpoints, such as a help desk-related user group, expand the **User Groups** section and click **Manage User Groups**.

15. Select the user group, then click **Select**.
16. If you want to configure individual users to establish screen sharing sessions with endpoints, expand the **Users** section and click **Manage Users**.
17. Select the users, then click **Select**.
18. Click **Save**.
    Tanium Console operators assigned this persona can establish unattended screen sharing sessions when this persona is active.

Open an endpoint screen sharing session

About this task

To open a screen sharing session, you must have access to the endpoint in Tanium, and the endpoint must have Screen Sharing tools installed using Tanium Endpoint Configuration unless you are connecting to an endpoint without a Tanium Client. After you initiate a connection, the connection screen for the endpoint shows the status. Establishing connections can take between one and three minutes.

Note:

- The ScreenMeet Remote Support client is included with the Screen Sharing endpoint tools. ScreenMeet actively supports Remote Support client versions released within the last two years. Older versions may continue to work but are no longer actively supported.
- After installing or upgrading Screen Sharing or Endpoint Configuration, or adding new endpoints to your environment, it might take several minutes for Endpoint Configuration to install Screen Sharing tools on an endpoint. If an endpoint does not have Screen Sharing tools installed, attempts to establish a screen sharing session with that endpoint fail. Wait several minutes for installation of Screen Sharing tools and then try again. For more information on Endpoint Configuration and endpoint tools, see Tanium Endpoint Configuration User Guide: Managing endpoint tools.

©2026 Tanium Inc. All Rights Reserved

You can establish an attended connection, which requires the endpoint user to accept the screen sharing connection, or an unattended connection, which allows you to establish the connection without endpoint user permission.

Important: Screen Sharing sessions are only established on endpoints that are included in the Screen Share action group. Therefore, the **Open Screen Sharing** button is only available for endpoints that are included in the Screen Share action group. By default, the action group is set to All Computers.

During the connection process, a ScreenMeet executable file is deployed to the endpoint with a Tanium Action. This executable file connects to the ScreenMeet services and establishes a connection with Tanium. The connection behavior depends on the endpoint operating system and whether you establish an attended or unattended connection:

- For attended connections to Windows endpoints, the endpoint user must accept the screen sharing session to continue. This establishes an active session and the Tanium Console operator takes control.
- For attended connections to macOS endpoints, if the endpoint user has allowed the proper screen sharing permissions on the endpoint, a view-only session is initially established. The Tanium Console operator must request control, and the endpoint user must accept, which then allows the operator to take control.
- For unattended connections to Windows endpoints, a new session is created without endpoint user permission and the Tanium Console operator takes control.
- Unattended connections to macOS endpoints are not supported.

Important: If PowerShell is in the `ConstrainedLanguage` language mode on Windows endpoints, the Screen Sharing script to open a user session (<Tanium Client installation directory>\Tools\ScreenSharing\start-session.ps1), which is signed, must be allowed to run in `FullLanguage` mode through Windows Defender application control (WDAC) or other system policies.

©2026 Tanium Inc. All Rights Reserved

Note:

If no endpoint users are logged in to an endpoint and you establish an unattended connection, after you enter operating system login information, the session displays a disconnection message. Wait several seconds for the login process to complete and reestablish the connection.


When you configure session recording in the ScreenMeet console (**Organization** > **Settings and Policies** > **Remote Support Features** > **Session Recording**), if you select:

- **Always**, the Tanium screen sharing session is always recorded.
- **Let the Agent Decide**, and the Tanium Console operator has the **Screen Sharing Product Options Read** permission, the Tanium Console operator has the option to record a screen sharing session. If the session is recorded, users have the option to disable recording before joining the session.
- **Never**, the Tanium screen sharing session is never recorded.

  For more information about configuring session recording, see ScreenMeet Docs: Remote Support Settings.

OPEN A SCREEN SHARING SESSION FROM AN ENDPOINT

1. From the Tanium **Home** page, go to **Search for endpoints** and type the IP address or computer name of the computer, then click the computer name.
2. Click **Open Screen Sharing session**.



3. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute** permission, you have the following options:
   - Select **Ask the endpoint user for permission** to start an attended session.
   - Clear **Ask the endpoint user for permission** to start an unattended session. After you end the session, by default, the endpoint locks.
4. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute**

©2026 Tanium Inc. All Rights Reserved


and **Screen Sharing Support Session Disable Autolock Execute** permissions, then start an unattended session, you have the following options:

- Select **Automatically lock after session ends** to lock the endpoint after you end the unattended session.
- Clear **Automatically lock after session ends** to leave the endpoint unlocked after you end the unattended session.

5. (Windows and macOS endpoints) If you have the **Screen Sharing Product Options Read** permission, and **Let the Agent Decide** is selected in the ScreenMeet console **Session Recording** settings, you have the following options:
   - Select **Record session** to record the screen sharing session. Users have the option to disable recording before joining the session.
   - Clear **Record session** to establish the screen sharing session without recording.
6. Click **Open**.
7. A Tanium action deploys to the endpoint that includes an executable file that connects to ScreenMeet services. Establishing connections can take between one and three minutes. If the attended session is on an end user's computer, the user must accept the session on the endpoint to continue.
8. When the screen sharing session is connected, your screen switches to ScreenMeet in Tanium. You can use Support Tools in ScreenMeet to run Windows commands, tasks, and tools.

OPEN A SCREEN SHARING SESSION FROM DIRECT CONNECT


1. **Shared Services** > **Integrations Gallery**
2. Go to the **Direct Connect to an Endpoint** section and select a search option to find the endpoint for which you want to start a connection:
   - **Simple**: Enter the IP address or computer name of the endpoint.



   - **Filter Builder**: Configure one or more sensor-based filters to find the endpoint. Select a sensor (such as **Last Logged In User**), select an operator (such as **contains**),

©2026 Tanium Inc. All Rights Reserved

enter the value to match, and click Apply ✓. For each additional filter, hover over Add +, select **Add Row** or **Add Group**, and repeat the configuration steps. Integrations Gallery processes group (nested) filters and applies Boolean AND/OR logic in the same way that Tanium Interact does for question results filters, and the configuration steps are similar. For more information, see Tanium Interact User Guide: Filter by advanced conditions.



3. In the result list, click **Open Screen Sharing session** for the endpoint.
4. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute** permission, you have the following options:
    - Select **Ask the endpoint user for permission** to start an attended session.
    - Clear **Ask the endpoint user for permission** to start an unattended session. After you end the session, by default, the endpoint locks.
5. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute** and **Screen Sharing Support Session Disable Autolock Execute** permissions, then start an unattended session, you have the following options:
    - Select **Automatically lock after session ends** to lock the endpoint after you end the unattended session.
    - Clear **Automatically lock after session ends** to leave the endpoint unlocked after you end the unattended session.
6. (Windows and macOS endpoints) If you have the **Screen Sharing Product Options Read** permission, and **Let the Agent Decide** is selected in the ScreenMeet console **Session Recording** settings, you have the following options:
    - Select **Record session** to record the screen sharing session. Users have the option to disable recording before joining the session.
    - Clear **Record session** to establish the screen sharing session without recording.
7. Click **Open**.

©2026 Tanium Inc. All Rights Reserved

8. A Tanium action deploys to the endpoint that includes an executable file that connects to ScreenMeet services. Establishing connections can take between one and three minutes. If the attended session is on an end user's computer, the user must accept the session on the endpoint to continue.
9. When the screen sharing session is connected, your screen switches to ScreenMeet in Tanium. You can use Support Tools in ScreenMeet to run Windows commands, tasks, and tools.


OPEN A SCREEN SHARING SESSION FROM REPORTING

About this task

Note: Tanium Reporting 1.43.40 or later is required to open screen sharing sessions in Reporting.

When you view, create, or edit a report that contains the **Computer Name** column, you can click an endpoint in the column to view details for the endpoint and to deploy an action to it. For information about Reporting, see Tanium Reporting User Guide: Working with a single endpoint.

1. Open a report that contains the **Computer Name** column.
2. Click Endpoint Details next to the name of an endpoint in the **Computer Name** column. An **Endpoint Details** dialog opens with basic details for the endpoint. If multiple endpoints have the same **Computer Name**, click Previous or Next in the **Multiple Results Found** banner to find the details for a specific endpoint.
3. Click **View Details** to open a page that shows a single endpoint view with detailed information.
4. Click **Open Screen Sharing session** to connect to the endpoint.




©2026 Tanium Inc. All Rights Reserved

5. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute** permission, you have the following options:
    - Select **Ask the endpoint user for permission** to start an attended session.
    - Clear **Ask the endpoint user for permission** to start an unattended session. After you end the session, by default, the endpoint locks.
6. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute** and **Screen Sharing Support Session Disable Autolock Execute** permissions, then start an unattended session, you have the following options:
    - Select **Automatically lock after session ends** to lock the endpoint after you end the unattended session.
    - Clear **Automatically lock after session ends** to leave the endpoint unlocked after you end the unattended session.
7. (Windows and macOS endpoints) If you have the **Screen Sharing Product Options Read** permission, and **Let the Agent Decide** is selected in the ScreenMeet console **Session Recording** settings, you have the following options:
    - Select **Record session** to record the screen sharing session. Users have the option to disable recording before joining the session.
    - Clear **Record session** to establish the screen sharing session without recording.
8. Click **Open**.
9. A Tanium action deploys to the endpoint that includes an executable file that connects to ScreenMeet services. Establishing connections can take between one and three minutes. If the attended session is on an end user's computer, the user must accept the session on the endpoint to continue.
10. When the screen sharing session is connected, your screen switches to ScreenMeet in Tanium. You can use Support Tools in ScreenMeet to run Windows commands, tasks, and tools.

OPEN A SCREEN SHARING SESSION FROM PERFORMANCE

1. From the Main menu, go to **Modules** > **Performance** > **Direct Connect**. Search for the endpoint by IP address, computer name, or by using the Filter Builder.
2. From the results list, click the name of the endpoint in the **Computer Name** column.
3. After a connection is established, click **Open Screen Sharing session**.

©2026 Tanium Inc. All Rights Reserved



4. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute** permission, you have the following options:
    - Select **Ask the endpoint user for permission** to start an attended session.
    - Clear **Ask the endpoint user for permission** to start an unattended session. After you end the session, by default, the endpoint locks.
5. (Windows endpoints) If you have the **Screen Sharing Support Session Unattended Execute** and **Screen Sharing Support Session Disable Autolock Execute** permissions, then start an unattended session, you have the following options:
    - Select **Automatically lock after session ends** to lock the endpoint after you end the unattended session.
    - Clear **Automatically lock after session ends** to leave the endpoint unlocked after you end the unattended session.
6. (Windows and macOS endpoints) If you have the **Screen Sharing Product Options Read** permission, and **Let the Agent Decide** is selected in the ScreenMeet console **Session Recording** settings, you have the following options:
    - Select **Record session** to record the screen sharing session. Users have the option to disable recording before joining the session.
    - Clear **Record session** to establish the screen sharing session without recording.
7. Click **Open**.
8. A Tanium action deploys to the endpoint that includes an executable file that connects to ScreenMeet services. Establishing connections can take between one and three minutes. If the attended session is on an end user's computer, the user must accept the session on the endpoint to continue.
9. When the screen sharing session is connected, your screen switches to ScreenMeet in Tanium. You can use Support Tools in ScreenMeet to run Windows commands, tasks, and tools.

OPEN A SCREEN SHARING SESSION WITH AN ENDPOINT THAT DOES NOT HAVE A TANIUM CLIENT

About this task


You can open screen sharing sessions initiated from Tanium with unmanaged endpoints. This option can be helpful if you need to connect to the endpoint to troubleshoot issues with the Tanium Client.

©2026 Tanium Inc. All Rights Reserved

In this scenario, the user at the endpoint must manually download and install the ScreenMeet files since they cannot be distributed using Tanium. To use this method, you must be assigned a role that includes either the **Screen Sharing Console** or **Screen Sharing Console Admin** permission.

> **Note:** Use this method to open a screen sharing session with a mobile device.

1. From the Tanium **Home** page, go to Navigate with quick links and enter **Direct Connect - ScreenMeet Console**.
   Click the **Direct Connect - ScreenMeet Console** quick link.



2. If you have more than one ScreenMeet product configured in your environment, click **Remote Support**.
3. Enter a **Description** for the session and configure the session options.

   > **Note:** Only the default ScreenMeet session options are available when you use this method to start the session.

4. Click **Create Session**.
5. Provide the user at the endpoint with the session URL and PIN code.
6. Ask the user at the endpoint to access the URL using a web browser and download and install the ScreenMeet client.
   For more information, see ScreenMeet documentation: Instructions to Person at End Point Device and ScreenMeet documentation: Providing Remote Support assistance to mobile devices.
7. After the user at the endpoint installs the ScreenMeet client and allows the session (if applicable), click **Enter Session** in the ScreenMeet console.

   > **Note:** The **Enter Session** button appears only when the user at the endpoint has installed the ScreenMeet client and allowed the session on the endpoint.

8. When the screen sharing session is connected, your screen switches to ScreenMeet in

©2026 Tanium Inc. All Rights Reserved

Tanium. You can use Support Tools in ScreenMeet to run Windows commands, tasks, and tools.

View and join screen sharing sessions

About this task

If you have **Integration Admin - ScreenMeet** role, you can see all sessions, and you can join sessions that were started by other Tanium Console operators.

If you have **Screen Sharing Agent** role, you can see and rejoin sessions that you started.

> **Note:** Multiple Tanium Console operators can join an endpoint screen sharing session, but only one operator at a time can take control of the session.

JOIN ACTIVE SESSIONS IN THE LIST OF SESSIONS

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**. The **Screen Sharing Sessions** section lists the active sessions.
3. Select one or more active sessions to an endpoint, then click **Join Screen Sharing** to join the sessions.

SEARCH FOR AN ENDPOINT TO JOIN THE ACTIVE SESSION

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**. Search for the computer by IP address or computer name.
2. In the result list, click **Join Screen Sharing** for the endpoint.

End an endpoint screen sharing session

When you stop a session, screen sharing processes are removed from the endpoint.

©2026 Tanium Inc. All Rights Reserved

Note: For attended connections to macOS endpoints, after the Tanium Console operator ends the session, a message is displayed to the endpoint user that the session is closed. The endpoint user must close the ScreenMeet application before a Tanium Console operator can establish another connection to that endpoint.

END ACTIVE SESSIONS IN THE LIST OF SESSIONS

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**. The **Screen Sharing Sessions** section lists the active sessions.
3. Select one or more endpoints and click **End Screen Sharing**.

SEARCH FOR AN ENDPOINT TO END THE ACTIVE SESSION

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**. Search for the computer by IP address or computer name.
2. In the result list, click **End Screen Sharing** for the endpoint.

Configure ScreenMeet settings

About this task

To configure settings in ScreenMeet, you must have a **Integration Admin - ScreenMeet** role. Users with the **Screen Sharing Agent** role can access the ScreenMeet console using a magic link but cannot configure organizational settings.

From the Main menu, go to **Shared Services >** Integrations Gallery. Click Settings and then click **Screen Sharing**. The following options are available:

- Click the **Open ScreenMeet Configuration** link to use a magic link to open an authenticated session in the ScreenMeet console. In the ScreenMeet console, you can view session history, detailed logging of actions taken during a session, and so on. For more information, see ScreenMeet Docs: Remote Support Settings.

©2026 Tanium Inc. All Rights Reserved

> **Note:** Opening the ScreenMeet console from Tanium Console allocates a per-operator license to your user account, regardless of whether you establish a screen sharing session with this account.

> **Note:** AI summarization of screen sharing sessions is controlled at the ScreenMeet organization level. Tanium Console has no setting to turn AI summaries on or off. If AI summarization is turned off in the ScreenMeet console, a summary is not generated for any session.

- In the **License Usage** section, click **Users** to expand the table and view a list of users allocated a per-user license, and the time that each user most recently signed in to Tanium Console.
- Click **Export** > **Export to CSV** to export a comma-separated value (CSV) file containing the list of users.
- Enter an **Alert Threshold** percentage to receive alerts in Tanium Console when the ratio of allocated per-user licenses to total licenses exceeds this percentage.

Move your Tanium Account

Troubleshoot the Screen Sharing integration

If the ScreenMeet Screen Sharing integration is not performing as expected, you might need to troubleshoot issues or change settings.

Collect logs

About this task

The information is saved as a ZIP file that you can download with your browser. The ZIP file is also known as a support bundle.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Screen Sharing Service Powered by ScreenMeet**.
3. Click **Support**.

©2026 Tanium Inc. All Rights Reserved

4. Click **Create Package**. An integrations-gallery-support-bundle-[timestamp].zip file downloads to the local download directory.
5. Contact Tanium Support to determine the best option to send the ZIP file. For more information, see View the Support page on page 115.

Result

Screen sharing buttons and related functionality might not be available in Tanium Console while the system rotates ScreenMeet key information. By default, this action occurs once every 30 days. Wait up to 30 minutes for this action to complete and then try accessing screen sharing functionality. For more information about next steps if you still cannot access screen sharing functionality, contact Tanium Support.

Screen sharing buttons unavailable

Screen sharing buttons and related functionality might not be available in Tanium Console while the system rotates ScreenMeet key information. By default, this action occurs once every 30 days. Wait up to 30 minutes for this action to complete and then try accessing screen sharing functionality. For more information about next steps if you still cannot access screen sharing functionality, contact Tanium Support.

Contact support

If you require assistance with ScreenMeet tools, contact ScreenMeet. For more information, see ScreenMeet support.

©2026 Tanium Inc. All Rights Reserved

Managing the ServiceNow integrations

Important:

To use ServiceNow integrations, you must be:

- a ServiceNow customer
- a Tanium on-premises customer

ServiceNow integrations allow you to combine Tanium information and functionality with the ServiceNow platform, based on the specific integration. You can configure one or multiple integrations from Integrations Gallery, based on your Tanium and ServiceNow deployments and licensing. Configuration generates required Tanium content for an integration, and an API token you can provide to the corresponding ServiceNow app in your ServiceNow instance.

Important: Each Tanium integration requires its own dedicated API token to ensure stable and secure communication. These tokens must be unique for each integration and for each ServiceNow environment. If you use multiple Tanium integrations across multiple ServiceNow environments (such as dev, test, and prod), you must generate a separate API token for each combination. This is essential because each integration manages its own token rotation. Reusing a token across integrations or environments might result in authentication conflicts, which can cause one integration to disrupt the other Tanium integrations.

Before you begin

- You must have a ServiceNow instance. The ServiceNow version depends on the specific integration.
- If you cannot establish a direct connection between Tanium and ServiceNow, deploy a ServiceNow management, instrumentation, and discovery (MID) server to establish communications between the ServiceNow instance and the Tanium Server and Tanium

©2026 Tanium Inc. All Rights Reserved

Module Server.

- Review ServiceNow integration dependencies to plan your installation and configuration. For more information, see .
- Configure network allow list rules to allow bidirectional traffic between the Tanium Server and the ServiceNow instance over port 443/TCP.

Requirements

Review the requirements before you configure the ServiceNow integrations.

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium™ Core Platform servers
- Tanium™ Client: No client requirements.
- Tanium™ Console

Solution dependencies

Other Tanium solutions are required for ServiceNow integrations to function (required dependencies) or for specific ServiceNow integrations to work (feature-specific dependencies). The installation method that you select determines if the Tanium Server automatically imports dependencies or if you must manually import them.

Note: Some ServiceNow integration dependencies have their own dependencies, which you can see by clicking the links in the lists of Required dependencies on page 133 and Feature-specific dependencies on page 134. Note that the links open the user guides for the latest version of each solution, not necessarily the minimum version that ServiceNow integrations require.

REQUIRED DEPENDENCIES

ServiceNow integrations have the following required dependencies:

©2026 Tanium Inc. All Rights Reserved

- Tanium™ Partner Integration

FEATURE-SPECIFIC DEPENDENCIES

> **Note:** Confirm that you have the applicable ServiceNow apps and other prerequisites for your integrations installed in the ServiceNow instance.

ServiceNow integrations have the following feature-specific dependencies:

ServiceNow integration	Feature-specific dependencies
Live UI	For more information, see Tanium Live UI User Guide: Requirements for Live UI in ServiceNow and ServiceNow Store: Tanium Live UI Links and documents .
Service Graph Connector	For more information, see Tanium IT Asset Management User Guide: Tanium IT Asset Management overview and ServiceNow Store: Service Graph Connector for Tanium Links and documents .
Tanium SDK	For more information, see ServiceNow Store: Tanium SDK Links and documents .
Vulnerability Management	For more information, see Tanium Vulnerability Management User Guide: Configuring ServiceNow for the Tanium Vulnerability Management integration and ServiceNow Store: Tanium Vulnerability Management Integration .

Third-party software

You must have a ServiceNow instance to configure integrations between Tanium and ServiceNow.

Host and network security requirements

Specific ports and processes are needed to run ServiceNow integrations.

Ports

The following ports are required for communication with ServiceNow.

©2026 Tanium Inc. All Rights Reserved

Source	Destination	Port	Protocol	Purpose
Module Server	ServiceNow instance	443	TCP	Establish a connection between the Module Server and ServiceNow instance

Best Practice: Configure firewall policies to open ports for Tanium traffic with TCP-based rules instead of application identity-based rules. For example, on a Palo Alto Networks firewall, configure the rules with service objects or service groups instead of application objects or application groups.

SECURITY EXCLUSIONS

If antivirus (AV) or other security software is in use in the environment to monitor and block unknown host system processes, Tanium requires that a security administrator create exclusions to allow the Tanium processes to run without interference. This software can include security applications that are included with an endpoint operating system, such as fapolicyd on some Linux distributions, or Microsoft Defender on Windows. The configuration of these exclusions varies depending on the security software.

No additional security exclusions are required.

User role requirements

Predefined roles grant the following permissions, which are required to use ServiceNow integration functionality:

- Table 27. Partner Integration solution permissions on page 136
- Table 28. Provided Partner Integration administration and platform content permissions on page 137: The solution permissions automatically provide some of these permissions.

Some ServiceNow integration solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to ServiceNow integrations. If you create custom roles for ServiceNow integration users, be sure to assign all the solution permissions and content set permissions that are required for ServiceNow integration functionality. If you are not sure which permissions are required for a custom role, view the

©2026 Tanium Inc. All Rights Reserved

permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)
- Provided role permissions
- View effective role permissions
- Configure a custom role

Note: Individual ServiceNow integrations have a system role associated with integration configuration. Assign the **Integration Operator - ServiceNow** system role and any integration-specific system roles to your account to configure each ServiceNow integration.

Note: Do not assign the **Partner Integration Service Account** and **Partner Integration Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

For more information about role permissions and associated content sets, see Tanium Console User Guide: RBAC overview.

Partner Integration solution permissions

Permission	Integration Operator - ServiceNow [1]	Integration Viewer - ServiceNow [1]
Partner Integration Access Integrations Gallery	✓ SHOW	✓ SHOW
Partner Integration API Use the Partner Integration API	✓ EXECUTE	✓ EXECUTE
Partner Integration Asset Report View Asset reports and views	✓ READ	✓ READ

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Operator - ServiceNow [1]	Integration Viewer - ServiceNow [1]
Partner Integration Connect Owner Update the owner of a Connect connection	✓ WRITE	✗
Partner Integration Connect Read Read all Connect connections	✗	✓ ALL
Partner Integration Connection Verify a Partner Integration connection with a third party	✓ VERIFY	✓ VERIFY
Partner Integration Credentials Access Partner Integration credentials	✓ READ	✓ READ
Partner Integration Gallery View the Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Servicenow View ServiceNow information in Integrations Gallery	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View metrics information in Integrations Gallery	✓ READ	✓ READ

[1] The permissions for these roles provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

Provided Partner Integration administration and platform content permissions

Permission	Permission Type	Integration Operator - ServiceNow	Integration Viewer - ServiceNow
Action Group	Administration	✓ READ	✓ READ

©2026 Tanium Inc. All Rights Reserved

Permission	Permission Type	Integration Operator - ServiceNow	Integration Viewer - ServiceNow
User	Administration	READ	READ
Filter Group	Platform Content	READ	READ
Package	Platform Content	READ	READ
Plugin	Platform Content	READ EXECUTE	READ EXECUTE
Sensor	Platform Content	READ	READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

View the Details page

About this task

The **Details** page for ServiceNow integrations shows the following information:

- **Service Enablement** toggle
- **ServiceNow Instances** count
- **Access** link
- **Usage** graph
- **Sync History** table

To view the **Details** page:

©2026 Tanium Inc. All Rights Reserved

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration.

View the Configuration page

About this task

The **Configuration** page for ServiceNow integrations shows relevant configuration information, based on the integration. This can include:

- **Integration Instance Configurations** table
- **Role Assignment**: For more information, see User role requirements on page 135.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration.
3. Click **Configuration**.

View the Tanium Content page

About this task

The **Tanium Content** page for ServiceNow integrations shows the following information:

- **Dashboard** summary panes
- **Reports** table

To view the **Tanium Content** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration.
3. Click **Tanium Content**.

©2026 Tanium Inc. All Rights Reserved

View the Support page

About this task

The **Support** page for the ServiceNow integrations shows the following information:

- **Create Package** button to create a troubleshooting package for support requests

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration.
3. Click **Support**.

View the About page

About this task

The **About** page for the ServiceNow integrations shows information related to that integration.

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration.
3. Click **About**.

Configuring the Live UI integration

The Tanium Live UI in ServiceNow (Live UI) integration allows you to view endpoint metrics and take actions on monitored endpoints from ServiceNow.

Before you begin with the Live UI integration

To configure Live UI, confirm that you have the applicable ServiceNow apps and other prerequisites for your integrations installed in the ServiceNow instance. For more information, see Tanium Live UI User Guide: Requirements for Live UI in ServiceNow.

©2026 Tanium Inc. All Rights Reserved

Live UI user role requirements

Predefined roles grant the following permissions, which are required to use ServiceNow integration functionality:

- Table 30. Provided Live UI integration platform content permissions on page 141
- Table 29. Live UI integration permissions on page 141: The solution permissions automatically provide some of these permissions.

Note: Assign the **Integration Operator - ServiceNow**, **ServiceNow Live UI**, **Interact Basic User**, and **Gateway User** system roles to each user that configures this integration. Do not assign these system roles to a user group, as users cannot configure the integration based solely on user group membership.

Note: Do not assign the **Partner Integration Service Account** and **Partner Integration Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

Live UI integration permissions

Permission	ServiceNow Live UI
Partner Integration API Use the Partner Integration API	✓ EXECUTE
Partner Integration Servicenow Heartbeat Post heartbeat messages to ServiceNow instances	✓ WRITE

Provided Live UI integration platform content permissions

Permission	Permission Type	ServiceNow Live UI
Plugin	Platform Content	✓ READ EXECUTE

©2026 Tanium Inc. All Rights Reserved

Permission	Permission Type	ServiceNow Live UI
To view the content sets to which the platform content permissions apply, see View effective role permissions .		

Enable the Live UI integration

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Live UI for ServiceNow**.
3. Click **Enable**.

Create a ServiceNow instance configuration for Live UI

About this task

By default, the API token that is generated when you create a ServiceNow instance is valid for 30 days, and is automatically rotated before the API token expires.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Live UI for ServiceNow**.
3. Click **Configuration**.
4. Click **Add Configuration**.
5. Select **Create a new instance** to create a new **Integration Instance** to associate with this configuration.

   Note: If you have an existing integration instance that is not already associated with a ServiceNow instance configuration, you can select that existing instance instead.
6. Enter an **Instance Name**, such as `My Company - ServiceNow Production`.
7. Enter the **ServiceNow URL** of your ServiceNow instance.
8. Enter an optional **Description**.
9. Select a **Content Set**.
10. Enter your ServiceNow instance IP address in **Trusted IP Addresses**.

©2026 Tanium Inc. All Rights Reserved

11. Click **Create**. In the Configuration Details for the ServiceNow Console window, copy the **Authentication Type** token value and **API Host Name** and paste each value in a plain text editor.

    Important:
    The token value includes the `token-` prefix. You must copy the token value before you can close the Configuration Details window.

    You cannot copy the token value after the visibility timeout expires (five minutes).

    A persona is created for and associated with each generated API token. The persona name starts with `ServiceNow`, followed by the ServiceNow integration name. You must assign the **ServiceNow Live UI**, **Interact Basic User**, and **Gateway User** system roles to this persona to grant necessary permissions for the generated API token.

12. After you copy the **Authentication Type** and **API Host Name** values, click **Close**.

    Note: In ServiceNow, configure the Tanium Live UI application. Provide the **Authentication Type** API token value on the system properties page. For more information, see Tanium Live UI User Guide: Configuring Live UI in ServiceNow.

Configuring the SDK for ServiceNow integration

The Tanium SDK for ServiceNow (SDK) provides software development interfaces for custom integration from ServiceNow to Tanium. In addition, several Tanium integrations with ServiceNow have a required dependency on the SDK.

Before you begin with the SDK integration

To configure the SDK, confirm that you have the applicable ServiceNow apps and other prerequisites for your integrations installed in the ServiceNow instance. For more information, see ServiceNow Store: Tanium SDK Links and documents.

SDK user role requirements

Predefined roles grant the following permissions, which are required to use ServiceNow integration functionality:

©2026 Tanium Inc. All Rights Reserved

- Table 31. SDK integration permissions on page 144
- Table 32. Provided SDK integration platform content permissions on page 144: The solution permissions automatically provide some of these permissions.

Note: Assign the **Integration Operator - ServiceNow**, **ServiceNow SDK**, **Interact Basic User**, **Gateway User**, and **Interact Power User** system roles to each user that configures this integration. Do not assign these system roles to a user group, as users cannot configure the integration based solely on user group membership.

Note: Do not assign the **Partner Integration Service Account** and **Partner Integration Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

SDK integration permissions

Permission	ServiceNow SDK
Partner Integration API Use the Partner Integration API	✓ EXECUTE
Partner Integration Servicenow Heartbeat Post heartbeat messages to ServiceNow instances	✓ WRITE

Provided SDK integration platform content permissions

Permission	Permission Type	ServiceNow SDK
Plugin	Platform Content	✓ READ EXECUTE

To view the content sets to which the platform content permissions apply, see View effective role permissions .

Enable the SDK integration

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.

©2026 Tanium Inc. All Rights Reserved

2. In the **Integrations** section, click **Tanium SDK for ServiceNow**.
3. Click **Enable**.

Create the ServiceNow instance configuration for SDK

About this task

By default, the API token that is generated when you create a ServiceNow instance is valid for 30 days, and is automatically rotated before the API token expires.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium SDK for ServiceNow**.
3. Click **Configuration**.
4. Click **Add Configuration**.
5. Select **Create a new instance** to create a new **Integration Instance** to associate with this configuration.

   > **Note:** If you have an existing integration instance that is not already associated with a ServiceNow instance configuration, you can select that existing instance instead.

6. Enter an **Instance Name**, such as `My Company - ServiceNow Production`.
7. Enter the **ServiceNow URL** of your ServiceNow instance.
8. Select a **Content Set**.
9. If you want to change the computer groups that ServiceNow can access through the SDK, click **Select Computer Groups**. Select additional computer groups and then click **Save**.
10. Enter your ServiceNow instance IP address in **Trusted IP Addresses**.
11. Click **Create**. In the Configuration Details for the ServiceNow Console window, copy the **Authentication Type** token value and paste the value in a plain text editor.

©2026 Tanium Inc. All Rights Reserved

> **Important:**
> The token value includes the `token-` prefix. You must copy the token value before you can close the Configuration Details window.
>
> You cannot copy the token value after the visibility timeout expires (five minutes).
>
> A persona is created for and associated with each generated API token. The persona name starts with `ServiceNow`, followed by the ServiceNow integration name. You must assign the **ServiceNow SDK**, **Interact Basic User**, and **Gateway User** system roles to this persona to grant necessary permissions for the generated API token.

12. After you copy the **Authentication Type** token value, click **Close**.

> **Note:** In ServiceNow, use the **Guided Setup** to configure the Tanium SDK application. Provide the **Authentication Type** API token value when prompted. For more information, see ServiceNow Store: Tanium SDK Links and documents.

Configuring the Service Graph Connector for Tanium integration

The ServiceNow Service Graph Connector for Tanium (Service Graph Connector) pulls inventory and usage data from Tanium Asset views into the ServiceNow configuration management database (CMDB), enhancing device management in ServiceNow.

Before you begin with the Service Graph Connector integration

To configure the Service Graph Connector, confirm that you have the applicable ServiceNow apps and other prerequisites for your integrations installed in the ServiceNow instance. For more information, see Tanium IT Asset Management User Guide: Tanium IT Asset Management overview.

Service Graph Connector user role requirements

Predefined roles grant the following permissions, which are required to enable and configure Service Graph Connector for Tanium:

- Table 33. Service Graph Connector integration permissions on page 147

©2026 Tanium Inc. All Rights Reserved

- Table 34. Provided Service Graph Connector administration and platform content permissions on page 148: The solution permissions automatically provide some of these permissions.

Assign the **Integration Operator - ServiceNow** and **ServiceNow Service Graph Connector** system roles to each user that configures this integration. Do not assign these system roles to a user group, as users cannot configure the integration based solely on user group membership.

Note: Do not add the user account that configures this integration to a user group that has Asset permissions assigned. Users in a user group with Asset permissions assigned might see incorrect graph data or metrics on the **Details** page.

Note: Do not assign the **Partner Integration Service Account** and **Partner Integration Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

Service Graph Connector integration permissions

Permission	ServiceNow Service Graph Connector [1]
Partner Integration API Use the Partner Integration API	✓ EXECUTE
Partner Integration Asset Report Allows users to view Asset reports and views	✓ READ
Partner Integration Servicenow Heartbeat Post heartbeat messages to ServiceNow instances	✓ WRITE

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

©2026 Tanium Inc. All Rights Reserved

Provided Service Graph Connector administration and platform content permissions

Permission	Permission Type	ServiceNow Service Graph Connector
Action Group	Administration	✓ READ
Filter Group	Platform Content	✓ READ
Plugin	Platform Content	✓ READ EXECUTE
Sensor	Platform Content	✓ READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

Enable the Service Graph Connector integration

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Service Graph Connector for Tanium**.
3. Click **Enable**.

Create a ServiceNow instance configuration for Service Graph Connector

About this task

By default, the API token that is generated when you create a ServiceNow instance is valid for 30 days and is automatically rotated before the API token expires.

Note: Assign the **Integration Operator - ServiceNow** and **ServiceNow Service Graph Connector** system roles to your account to configure this integration.

©2026 Tanium Inc. All Rights Reserved

1. Sign in to Tanium Console.
2. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
3. In the **Integrations** section, click **Service Graph Connector for Tanium**.
4. Click **Configuration**.
5. Click **Add Configuration**.
6. Select **Create a new instance** to create an **Integration Instance** to associate with this configuration.

   Note: If you have an existing integration instance that is not already associated with a ServiceNow instance configuration, you can select that existing instance instead.

7. Enter an **Instance Name**, such as `My Company - ServiceNow Production`.
8. Enter the **ServiceNow URL** of your ServiceNow instance.
9. Enter an optional **Description**.
10. Select a **Content Set**.
11. Associate an Asset view with this integration instance to send data to ServiceNow:
    - Select **Create a new view** to create a new view with the required settings.
    - Select **Assign an existing view** and then select an Asset view.
12. Enter your ServiceNow instance IP address in **Trusted IP Addresses**.
13. Click **Create**. In the Configuration Details for the ServiceNow Console window, copy the **Authentication Type** token value and **API Host Name** and paste each value in a plain text editor.

    Important:
    The token value includes the `token-` prefix. You must copy the token value before you can close the Configuration Details window.

    You cannot copy the token value after the visibility timeout expires (five minutes).

    A persona is created for and associated with each generated API token. The persona name starts with `ServiceNow`, followed by the ServiceNow integration name.

©2026 Tanium Inc. All Rights Reserved

14. After you copy the **Authentication Type** and **API Host Name** values, click **Close**.

> **Note:** In ServiceNow, use the **Guided Setup** to configure the Service Graph Connector for Tanium application. Provide the **Authentication Type** API token value when prompted. For more information, see Tanium IT Asset Management User Guide: Configuring Service Graph Connector for Tanium.

Configuring the Vulnerability Management integration

The Tanium Vulnerability Management for ServiceNow (Vulnerability Management) integration pushes Comply vulnerability data to the ServiceNow CMDB, which you can then view in ServiceNow.

Before you begin with the Vulnerability Management integration

To configure Vulnerability Management, confirm that you have the applicable ServiceNow apps and other prerequisites for your integrations installed in the ServiceNow instance. For more information, see Tanium Vulnerability Management for ServiceNow User Guide: Tanium Vulnerability Management for ServiceNow overview.

Vulnerability Management user role requirements

Predefined roles grant the following permissions, which are required to use ServiceNow integration functionality:

- Table 35. Vulnerability Management integration permissions on page 151
- Table 36. Provided Vulnerability Management integration platform content permissions on page 151: The solution permissions automatically provide some of these permissions.

> **Note:** Assign the **Integration Operator - ServiceNow** and **ServiceNow Vulnerability Management** system roles to each user that configures this integration. Do not assign these system roles to a user group, as users cannot configure the integration based solely on user group membership.

©2026 Tanium Inc. All Rights Reserved

Note: Do not assign the **Partner Integration Service Account** and **Partner Integration Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

Vulnerability Management integration permissions

Permission	ServiceNow Vulnerability Management
Partner Integration API Use the Partner Integration API	✓ EXECUTE
Partner Integration Servicenow Heartbeat Post heartbeat messages to ServiceNow instances	✓ WRITE

Provided Vulnerability Management integration platform content permissions

Permission	Permission Type	ServiceNow Vulnerability Management
Plugin	Platform Content	✓ READ EXECUTE
To view the content sets to which the platform content permissions apply, see View effective role permissions .		

Enable the Vulnerability Management integration

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Vulnerability Management for ServiceNow**.
3. Click **Enable**.

   Note: Wait several minutes before continuing. After you enable the Vulnerability Management integration, the **Comply - CVE Findings** sensor is automatically registered with Tanium Data Service. This sensor is required to create a ServiceNow instance for Vulnerability Management.

Create a ServiceNow instance for Vulnerability Management

©2026 Tanium Inc. All Rights Reserved

About this task

By default, the API token that is generated when you create a ServiceNow instance is valid for 30 days, and is automatically rotated before the API token expires.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Vulnerability Management for ServiceNow**.
3. Click **Configuration**.
4. Click **Add Configuration**.
5. Select **Create a new instance** to create a new **Integration Instance** to associate with this configuration.

   > **Note:** If you have an existing integration instance that is not already associated with a ServiceNow instance configuration, you can select that existing instance instead.

6. Enter an **Instance Name**, such as `My Company - ServiceNow Production`.
7. Enter the **ServiceNow URL** of your ServiceNow instance.
8. Enter an optional **Description**.
9. Select a **Content Set**.
10. If you do not have existing Connect connections to assign to this configuration, enter a **ServiceNow Username** and associated **Password**, used to establish communications between the Connect connections and ServiceNow.
11. Associate two Connect connections with this integration instance, one using the **Tanium Comply (Findings)** source, one using the **Tanium Reporting (Source Data)** source to send CVE status:
    - Select **Create a new connection** to create a new connection with the required settings. Enter a **ServiceNow Username** and associated **Password** to enable the connection to establish communications with your ServiceNow instance.
    - Select **Assign an existing connection** and then select a **Connection**.
12. If you want to change the computer groups that ServiceNow can access for Vulnerability Management, click **Select Computer Groups**. Select additional computer groups and then click **Save**.

©2026 Tanium Inc. All Rights Reserved

13. Enter your ServiceNow instance IP address in **Trusted IP Addresses**.
14. Click **Create**. In the Configuration Details for the ServiceNow Console window, copy the **Authentication Type** token value and paste the value in a plain text editor.

    Important:
    The token value includes the `token-` prefix. You must copy the token value before you can close the Configuration Details window.

    You cannot copy the token value after the visibility timeout expires (five minutes).

    A persona is created for and associated with each generated API token. The persona name starts with `ServiceNow`, followed by the ServiceNow integration name.

15. After you copy the **Authentication Type** and **API Host Name** values, click **Close**.

    Note: In ServiceNow, use the **Guided Setup** to configure the Service Graph Connector for Tanium application. Provide the **Authentication Type** API token value when prompted. For more information, see Tanium Vulnerability Management User Guide: Configuring ServiceNow for the Tanium Vulnerability Management integration.

Updating ServiceNow instance configuration

You can update a ServiceNow instance if you want to update the display name or change references to Tanium content. You can delete a ServiceNow instance if you no longer want to send data to ServiceNow using an instance.

Edit a ServiceNow instance

About this task

Edit an integration instance configuration to update the configuration information.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration and then click **Configuration**.
3. Click Edit next to an integration instance.

©2026 Tanium Inc. All Rights Reserved

4. Configure the settings.
5. Click **Save**.

Delete a ServiceNow instance

About this task

Deleting a ServiceNow instance configuration disables sending information between Tanium to ServiceNow.

Important: Deleting a ServiceNow instance configuration also deletes all objects that have been created for this integration, which might include API tokens, personas, and other Tanium content. Other ServiceNow integrations with a dependency on this integration might stop working if you delete this ServiceNow instance configuration. Confirm that deleting this does not impact other ServiceNow integrations before continuing.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration and then click **Configuration**.
3. Click Delete for the ServiceNow instance configuration that you want to delete.

Troubleshooting ServiceNow integrations

If ServiceNow integrations are not performing as expected, you might need to troubleshoot issues or change settings.

Collect logs

About this task

The information is saved as a ZIP file that you can download with your browser. The ZIP file is also known as a support bundle.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. Click the tile associated with the ServiceNow integration.

©2026 Tanium Inc. All Rights Reserved

3. Click **Service Graph Connector for Tanium**.
4. Click **Tanium AI Agent for ServiceNow**.
5. Click **Tanium Live UI for ServiceNow**.
6. Click **Tanium SDK for ServiceNow**.
7. Click **Tanium Vulnerability Management for ServiceNow**.
8. Click **Support**.
9. Click **Create Package**.
   An integrations-gallery-support-bundle.[timestamp].zip file downloads to the local download directory.
10. Contact Tanium Support to determine the best option to send the ZIP file. For more information, see Contact support on page 221.

Cannot establish connection between Tanium and ServiceNow

If you cannot establish a connection between Tanium and ServiceNow, verify that the network traffic is allowed. Configure network allow list rules to allow bidirectional traffic between the Tanium Server and the ServiceNow instance over port 443/TCP.

API token is expired

About this task

API tokens generated for ServiceNow integrations expire after 30 days. ServiceNow rotates API tokens for integrations on a regular basis, generally every seven days. In rare circumstances, an API token might expire without being rotated, such as for extended ServiceNow outage. In this case, a notification banner appears for the integration, noting that one or more integration instance configurations are not associated with a valid API token.

In this case, you can manually generate a new API token, then copy the token value and paste it in ServiceNow to update the integration configuration.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click the name of the ServiceNow integration and then click **Configuration**.

©2026 Tanium Inc. All Rights Reserved

3. Click Options next to an integration instance and then click **Generate new API token**.
4. Confirm the selection.
5. Click Copy  next to the Token **Authentication Type** and paste the token value in a plain text editor.
6. Click **Close**.
7. In ServiceNow, update the API token value for the integration with the newly generated API token.

Contact Tanium Support

To contact Tanium Support for help, sign in to the Tanium Customer Community.

For more information about submitting a support case, see Case Submission Form.

©2026 Tanium Inc. All Rights Reserved

Managing the Slack integration with Jump Gate

Important:

To use the Tanium integration with Slack, you must be:

- a Slack subscriber
- a Tanium on-premises customer

For more information, see Slack documentation: Slack plans and features.

The Tanium integration with Slack enables notifications from Tanium Jump Gate to a configured Slack channel, based on supported Tanium functionality.

Requirements

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium™ Core Platform servers
- Tanium™ Client: No client requirements.

Required dependencies

The Slack integration has the following required dependencies:

- Tanium Partner Integration

©2026 Tanium Inc. All Rights Reserved

Feature-specific dependencies

Note: The Slack integration does not appear unless you install Tanium Jump Gate.

- Tanium Jump Gate to send notifications to Slack when a request is ready for approval

User role and persona requirements

The following tables list the role permissions required to configure the Slack integration. To review a summary of the predefined roles, see User role and persona requirements on page 158.

For more information about role permissions and associated content sets, see Tanium Console User Guide: RBAC overview.

Slack user role permissions

Permission	Integration Operator - Slack [1]	Integration Viewer - Slack [1]
Partner Integration View the Integrations Gallery workbench	✓ SHOW	✓ SHOW
Partner Integration Api Use the Integrations Gallery API	✓ EXECUTE	✓ EXECUTE
Partner Integration Connection Confirm connection with an integration	✓ VERIFY	✓ VERIFY
Partner Integration Credentials View and configure the Integrations Gallery credentials	✓ READ WRITE	✓ READ
Partner Integration Gallery View the Integrations Gallery	✓ READ	✓ READ

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Operator - Slack [1]	Integration Viewer - Slack [1]
Partner Integration Gallery Slack View the Slack settings in Integrations Gallery	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View reporting metrics in Integrations Gallery	✓ READ	✓ READ

[1] This role provides module permissions for Tanium Reporting. You can view which Reporting permissions are granted to this role in Tanium Console. For more information, see Tanium Reporting User Guide: User role requirements .

Provided Slack administration and platform content permissions

Permission	Permission Type	Integration Operator - Slack	Integration Viewer - Slack
Action Group	Administration	✓ READ	✓ READ
Filter Group	Platform	✓ READ	✓ READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

View the Details page

About this task

The **Details** page for the Slack integration shows the following information:

- **Service Enablement** toggle
- **Configuration** status
- **Usage** reports

To view the **Details** page:

©2026 Tanium Inc. All Rights Reserved

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Slack for Jump Gate**.

View the Configuration page

About this task

The **Configuration** page for the Slack integration shows the following information:

- **Register Tanium with Slack** configuration
- **Role Assignment**: For more information, see User role and persona requirements on page 158.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Slack for Jump Gate**.
3. Click **Configuration**.

View the About page

About this task

The **About** page for the Slack integration shows the following information:

- **Integrate with Jump Gate**
- **Requirements**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Slack for Jump Gate**.
3. Click **About**.

©2026 Tanium Inc. All Rights Reserved

Configure Slack integration with Tanium Jump Gate

About this task

To configure the Slack integration with Tanium Jump Gate:

1. Configure a Slack app to provide notifications in Slack, and a Slack configuration in Tanium to pass information from Tanium to Slack. For more information, see Create a Slack configuration on page 161.
2. Configure a Jump Gate access policy and enable external notifications. For more information, see Tanium Cloud User Guide: Configuring network egress for Tanium Cloud.

Result

Note: To allow Slack notifications from Tanium Core Platform, configure a network egress allow list rule to allow outbound traffic from Tanium to Slack for the sFQDN slack.com over port 443/TCP.

Enable the Slack integration

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Slack for Jump Gate**.
3. Click **Enable** and then confirm your selection.

Create a Slack configuration

About this task

Create a Slack configuration to connect to a Slack app to provide notifications in Slack. You can create a configuration for each Slack workspace where you want to provide notifications.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Slack for Jump Gate**.
3. Click **Create Slack configuration**.
4. Click **Copy Manifest** to copy the application manifest to use in creating the Slack app to provide notifications.

©2026 Tanium Inc. All Rights Reserved

Keep this configuration page open while you complete the next steps in your Slack API environment.

5. In your Slack API environment, create a new Slack app from the manifest you copied. For the steps, see Slack Developers docs: Creating apps using manifests.
6. Install the **tanium-notification-app** app you created in the previous step to your Slack workspace. For the steps, see Slack Developers docs: Installing and authorizing the app.
7. To obtain the OAuth token for the app, from the **OAuth & Permissions** settings in your Slack API environment, copy the **Bot User OAuth Token**.
8. Return to the configuration page in Tanium Console, and paste the **Slack Bot User OAuth Token** you copied in the previous step. Click **Save**.

Edit a Slack instance

About this task

Edit a Slack configuration to update the display **Name**, **Domain**, or OAuth **Token**.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Slack for Jump Gate** and then click **Configuration**.
3. Click Edit Slack Configuration next to a Slack configuration.
4. Configure the settings.
5. Click **Save**.

Delete a Slack instance

About this task

Deleting a Slack configuration disables sending future notifications from Tanium to Slack.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Slack for Jump Gate** and then click **Configuration**.
3. Click Delete Slack Configuration for the Slack configuration that you want to delete.

©2026 Tanium Inc. All Rights Reserved

Troubleshoot issues

If the Slack integration is not performing as expected, you might need to troubleshoot issues or change settings.

Cannot create the Slack app

Ensure that your Slack subscription plan does not restrict the number of apps that you can create. For more information, see Slack documentation: Slack plans and features.

Cannot establish a connection between Tanium and Slack

Ensure that a network egress allow list rule allows outbound traffic from Tanium to Slack for the the FQDN slack.com over port 443/TCP.

Cannot authorize the connection between Tanium and Slack

Ensure that you entered the OAuth token value for the created app when configuring the integration.

The Network Egress Allow List was not updated

After you save the Slack configuration, a warning states that the Network Egress Allow List was not updated.

©2026 Tanium Inc. All Rights Reserved

Managing the Tanium Connector for Microsoft Intune

Important:

To use the Tanium Connector for Microsoft Intune, you must be:

- A Microsoft Intune subscriber
- A Tanium on-premises customer

For more information about Microsoft Intune, see Microsoft Intune documentation: What is Microsoft Intune?.

The Tanium Connector for Microsoft Intune entity provider integrates a Microsoft Intune instance with Tanium to ingest mobile device data. Ingesting Intune mobile device data alongside other endpoints in your network allows you to better manage all endpoints in Tanium Console, instead of using multiple endpoint management methods. You can view mobile devices managed using Tanium Connector for Microsoft Intune in Tanium Console alongside devices managed using Tanium Client.

Important: In the context of the Tanium Connector for Microsoft Intune, devices that run Android, ChromeOS, iOS, and iPadOS are considered mobile devices. Conversely, laptops and other devices that support running Tanium Client are not considered mobile devices.

Before you begin

- You must have a Microsoft Intune subscription. There should be at least one mobile device enrolled.
    - Microsoft Intune requires a license. For more information, see Microsoft Intune documentation: Microsoft Intune licensing.

©2026 Tanium Inc. All Rights Reserved

    - Microsoft Intune supports mobile devices running Android, ChromeOS, iOS, or iPadOS. For more information, see Microsoft Intune documentation: Configure Chrome Enterprise connector, Microsoft Intune documentation: Enrollment guide: Enroll Android devices in Microsoft Intune, and Microsoft Intune documentation: Enrollment guide: Enroll iOS and iPadOS devices in Microsoft Intune.

- You must create an app registration for your Microsoft Intune instance. For more information, see Microsoft Entra documentation: Register an application in Microsoft Entra ID. As you complete the steps, make sure you do the following:

    - Copy the **Application (client) ID** and **Directory (tenant) ID** values to a plain text editor.

    - Assign permission scopes to the app registration. For more information, see Microsoft Intune documentation: How to use Microsoft Entra ID to access the Intune APIs in Microsoft Graph and Microsoft Intune documentation: Intune permission scopes.

Microsoft Intune app registration permission scope	Description
DeviceManagementManagedDevices.Read.All	Read Microsoft Intune device data and ingest device data into Tanium Core Platform
DeviceManagementConfiguration.ReadWrite.All	Read Microsoft Intune device configuration and policies and apply remote actions from Tanium Core Platform
DeviceManagementManagedDevices.ReadWrite.All	Read Microsoft Intune device data and apply remote actions from Tanium Core Platform
DeviceManagementManagedDevices.PrivilegedOperations.All	Apply user-impacting remote actions from Tanium Core Platform
DeviceManagementRBAC.Read.All	Read Microsoft Intune role scope tags

    - Grant admin consent to the app registration to allow the Tanium Connector for

©2026 Tanium Inc. All Rights Reserved

Microsoft Intune permission to access the Microsoft Intune instance. For more information, see [Microsoft Intune documentation: Grant admin consent (external tenants only)](#).

> **Note:** The **Global Administrator** role has permission to grant admin consent.

- Add a client secret or public key certificate application credential to the app registration. For more information, see [Microsoft Entra documentation: Add and manage application credentials in Microsoft Entra ID](#).

> **Note:** Public key certificates must be in PEM format.

- Configure network allow list rules to allow bidirectional traffic between the Tanium Server and a Microsoft Graph endpoint over port 443/TCP.

Microsoft Cloud Environment	Allowed endpoint [1]	Description
global environment	https://graph.microsoft.com/<api_version>/deviceManagement/<api_version>/<api_version>	Retrieve Microsoft Intune managed mobile device information
	https://graph.microsoft.com/<api_version>/deviceManagement/managedDevices	Send a remote action from Tanium to Microsoft Intune
	https://graph.microsoft.com/<api_version>/deviceManagement/remoteActionAudits	Retrieve Microsoft Intune audit log

©2026 Tanium Inc. All Rights Reserved

Microsoft Cloud Environment	Allowed endpoint [1]	Description
		information for remote actions taken on mobile devices
	https://graph.microsoft.com/<api_version>/deviceManagement/reports	Retrieve Microsoft Intune policy information
	https://login.microsoftonline.com	Authenticate the connection between Tanium Connector for Microsoft Intune and Microsoft Intune instance
	[1] Endpoint URLs might include the API version, such as v1.0, or other alphanumeric strings.	

Entities and endpoints

An *entity* is any discrete unit or node on a computer network that can be tracked, such as an endpoint, compute instance, cloud service, or identity object such as a user or group.

An *endpoint* is a computing device or node that connects to a computer network, through which data can enter or exit the network. Endpoints are a subset of entities; all endpoints are entities, but not all entities are endpoints. Endpoints include physical or virtual workstations that run Windows, macOS,

©2026 Tanium Inc. All Rights Reserved

or Linux, mobile devices that run Android or iOS, and other similar devices. In contrast, routers and switches are entities, but not endpoints, because routers and switches direct network traffic through the network, but do not provide a direct entry or exit point for data.

Entity providers

You can ingest data from endpoints managed using Tanium Client or an entity provider into the same Tanium instance to gain broader visibility into your entire network.

An *entity provider* is an adapter that ingests entity data into Tanium Core Platform. Tanium Core Platform uses this data to manage the entity. Entity providers collect entity data without installing Tanium Client on the endpoint. For example, you cannot install Tanium Client on mobile devices that run Android or iOS. You can configure the Tanium Connector for Microsoft Intune to integrate with a Microsoft Intune instance to ingest mobile device data or enroll Apple devices with Device Management.

- Management using Tanium Client: Tanium Client runs on endpoints that run a compatible operating system (OS), such as computers or virtual machines that run Linux, macOS, or Windows. These endpoints are generally part of the linear chain. Tanium Client reports information back to Tanium Core Platform through the linear chain.
- Management using entity providers, which collect device information in different ways:
    - Through integrations, such as the Tanium Connector for Microsoft Intune that ingests Microsoft Intune mobile device data

  Management of these devices does not rely on Tanium Client being installed directly on an entity. The entity provider might report endpoint information that is different from the information that a Tanium Client reports, due to the difference in entity type. For example, mobile devices are assigned an International Mobile Equipment Identity (IMEI) serial number, which are not assigned to other types of devices, such as an endpoint that runs Windows Server.

Each entity is associated with a **Provider Type**, **Provider Name**, and **Entity Type**, which identify how Tanium Core Platform manages the entity.

©2026 Tanium Inc. All Rights Reserved

Entity providers and related sensor values

Entity Provider	Provider Type value	Provider Name value	Entity Type value
Tanium Client	Tanium Client	Tanium	Computer
Tanium Endpoint Management for Mobile	Device Management	• Device Management Computer (for macOS) • Device Management Mobile Device (for iOS and iPadOS)	• Computer (for macOS) • Mobile Device (for iOS and iPadOS)

Architecture

The Tanium Connector for Microsoft Intune establishes a secure connection with a Microsoft Intune instance and retrieves mobile device data from Microsoft Intune. This data is cached in Tanium Core Platform. During the first connection to the Microsoft Intune instance, the Tanium Connector for Microsoft Intune retrieves all mobile device data and updates Tanium Core Platform with this information. Once every two minutes, the Tanium Connector for Microsoft Intune incrementally synchronizes only with managed devices that have checked in with Intune, retrieving changes for only those managed devices, and updates Tanium Core Platform with this information. Once every eight hours after the initial synchronization, the Tanium Connector for Microsoft Intune synchronizes with the Microsoft Intune instance, retrieves the devices that have been removed from the Microsoft Intune instance, and removes those device from Tanium Core Platform.


Note: Depending on the number of mobile devices that the Microsoft Intune instance manages, the initial synchronization might take several minutes or longer to complete. Subsequent synchronizations are faster than the initial synchronization, but might take several minutes or longer to complete.

Tanium operators that issue questions in Tanium Console can target all types of managed entities, including endpoints managed using Tanium Connector for Microsoft Intune and endpoints managed using Tanium Client. Tanium operators can also include endpoints managed using Tanium Connector for Microsoft Intune in Tanium Reporting reports and dashboards, or export the data using Tanium Connect.

©2026 Tanium Inc. All Rights Reserved

Tanium operators can issue remote actions from Tanium Console to endpoints managed using Tanium Connector for Microsoft Intune. The Tanium Connector for Microsoft Intune sends the remote action request to the Microsoft Intune instance. The Microsoft Intune instance applies the remote action to the targeted mobile device, subject to Microsoft Intune requirements for applying remote actions to mobile devices. For more information, see Microsoft Intune documentation: Device actions.

Figure 3. Example Tanium Connector for Microsoft Intune architecture



Requirements

Review the requirements before you install and use the Tanium Connector for Microsoft Intune.

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium license that includes an Endpoint Management Standard or Endpoint Management Plus bundle, which includes the Tanium Connector for Microsoft Intune. For more information about how to get an Endpoint Management bundle and Tanium Connector for Microsoft Intune, see Tanium Solutions & Bundles.

  Important: If you obtained your Tanium license prior to May 2025, you must update your license prior to configuring the Tanium Connector for Microsoft Intune. For more information, contact Tanium support.

©2026 Tanium Inc. All Rights Reserved

> **Note:** Mobile devices ingested using the Tanium Connector for Microsoft Intune do not count against endpoint licensing totals.

- Tanium™ Core Platform servers
- Tanium™ Client: No client requirements.
- Tanium™ Console

Solution dependencies

Other Tanium solutions are required for the Tanium Connector for Microsoft Intune to function (required dependencies) or for specific Tanium Connector for Microsoft Intune features to work (feature-specific dependencies). The installation method that you select determines if the Tanium Server automatically imports dependencies or if you must manually import them.

> **Note:** Some Tanium Connector for Microsoft Intune dependencies have their own dependencies, which you can see by clicking the links in the lists of Required dependencies on page 171 and Feature-specific dependencies on page 171. Note that the links open the user guides for the latest version of each solution, not necessarily the minimum version that the Tanium Connector for Microsoft Intune requires.

REQUIRED DEPENDENCIES

The Tanium Connector for Microsoft Intune has the following required dependencies:

- Tanium™ Asset
- Tanium™ Endpoint Provider Service

FEATURE-SPECIFIC DEPENDENCIES

If you select only Endpoint Provider to import, you must manually import or update its feature-specific dependencies regardless of Tanium Console or Tanium Core Platform versions. The Tanium Connector for Microsoft Intune has the following feature-specific dependencies:

©2026 Tanium Inc. All Rights Reserved

- Tanium™ Interact to ask questions and retrieve Microsoft Intune mobile device data
- Tanium™ Connect to export Microsoft Intune mobile device data to a destination

  Tanium™ Reporting to include Microsoft Intune mobile device data in reports and dashboards

Endpoints

Supported Internet protocols

The Tanium Connector for Microsoft Intune supports IPv4 and IPv6 addresses.

Supported operating systems

The following endpoint operating systems are supported with the Tanium Connector for Microsoft Intune.

- Android
- ChromeOS
- iPadOS
- iOS

For more information about supported operating systems, see Microsoft Intune documentation: Supported operating systems and browsers in Intune.

The Tanium Connector for Microsoft Intune does not install the Tanium Client or deploy packages to endpoints. For more information about Tanium Client operating system support, see Tanium Client Management User Guide: Client version and host system requirements.

Device requirements

For more information about mobile device minimum requirements, see Microsoft Intune: Configure Chrome Enterprise connector, Microsoft Intune: Enrollment guide: Enroll Android devices in Microsoft Intune, and Microsoft Intune: Enrollment guide: Enroll iOS and iPadOS devices in Microsoft Intune.

©2026 Tanium Inc. All Rights Reserved

Third-party software

You must have a Microsoft Intune subscription to use the Tanium Connector for Microsoft Intune. For more information about Microsoft Intune licensing, see Microsoft Intune: Microsoft Intune licensing.

Host and network security requirements

Specific ports and processes are needed to run the Tanium Connector for Microsoft Intune.

Ports

The following ports are required for Tanium Connector for Microsoft Intune communication.

Source	Destination	Port	Protocol	Purpose
Module Server	Microsoft Intune instance	443	TCP	Establish a connection between the Module Server and Microsoft Intune



Best Practice: Configure firewall policies to open ports for Tanium traffic with TCP-based rules instead of application identity-based rules. For example, on a Palo Alto Networks firewall, configure the rules with service objects or service groups instead of application objects or application groups.

For more information about Tanium Cloud ports, see Host and network security requirements.

SECURITY EXCLUSIONS

If antivirus (AV) or other security software is in use in the environment to monitor and block unknown host system processes, Tanium requires that a security administrator create exclusions to allow the Tanium processes to run without interference. This software can include security applications that are included with an endpoint operating system, such as fapolicyd on some Linux distributions, or Microsoft Defender on Windows. The configuration of these exclusions varies depending on the security software.

No additional security exclusions are required.

©2026 Tanium Inc. All Rights Reserved

User role requirements

Predefined roles grant the following permissions, which are required to use Tanium Connector for Microsoft Intune functionality:

- Table 40. Tanium Connector for Microsoft Intune solution permissions on page 174
- Tanium Connector for Microsoft Intune administration, platform content, and global permissions on page 176: The solution permissions automatically provide some of these permissions.

Some Tanium Connector for Microsoft Intune solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to Tanium Connector for Microsoft Intune. If you create custom roles for Tanium Connector for Microsoft Intune users, be sure to assign all the solution permissions and content set permissions that are required for Tanium Connector for Microsoft Intune functionality. If you are not sure which permissions are required for a custom role, view the permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)
- Provided role permissions
- View effective role permissions
- Configure a custom role

Note: Do not assign the **Endpoint Provider Service Account** and **Endpoint Provider Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

Tanium Connector for Microsoft Intune solution permissions

Permission	Integration Operator - Microsoft Intune [1]	Integration Viewer - Microsoft Intune [1]
Partner Integration Access Integrations Gallery	✓	✓

©2026 Tanium Inc. All Rights Reserved

Permission	Integration Operator - Microsoft Intune [1]	Integration Viewer - Microsoft Intune [1]
	SHOW	SHOW
Partner Integration API Use the Partner Integration API	✓ EXECUTE	✓ EXECUTE
Partner Integration Connection Verify a Partner Integration connection with a third party	✓ VERIFY	✓ VERIFY
Partner Integration Credentials Access Partner Integration credentials	✓ READ WRITE	✓ READ WRITE
Partner Integration Gallery View the Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Intune View Microsoft Intune information in Integrations Gallery	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View metrics information in Integrations Gallery	✓ READ	✓ READ

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

Endpoint Provider user role permissions

Permission	Mobile High Impact Action User	Mobile Action User	Mobile Viewer
Endpointprovider Administrate Endpoint Provider	✗	✗	✗

©2026 Tanium Inc. All Rights Reserved

Permission	Mobile High Impact Action User	Mobile Action User	Mobile Viewer
Endpointprovider API Use the Endpoint Provider API	✓ EXECUTE	✓ EXECUTE	✓ EXECUTE

Tanium Connector for Microsoft Intune administration and platform content permissions

Permission	Permission Type	Integration Operator - Microsoft Intune	Integration Viewer - Microsoft Intune
Action Group	Administration	✓ READ	✓ READ
Filter Group	Platform Content	✓ READ	✓ READ
Package	Platform Content	✓ READ	✓ READ
Plugin	Platform Content	✓ READ EXECUTE	✓ READ EXECUTE
Sensor	Platform Content	✓ READ	✓ READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

Endpoint Provider platform content permissions

Permission	Permission Type	Mobile High Impact Action User	Mobile Action User	Mobile Viewer
Action	Platform Content	✓ READ WRITE	✓ READ WRITE	✓ READ
Own Action	Platform Content	✓	✓	✗

©2026 Tanium Inc. All Rights Reserved

Permission	Permission Type	Mobile High Impact Action User	Mobile Action User	Mobile Viewer
		READ	READ	
Package	Platform Content	✓ READ	✓ READ	✗
Plugin	Platform Content	✓ READ EXECUTE	✓ READ EXECUTE	✓ READ EXECUTE
Sensor	Platform Content	✓ READ	✓ READ	✓ READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

View the Details page

About this task

The **Details** page for the Tanium Connector for Microsoft Intune shows the following information:

- **Service Enablement** toggle
- **Microsoft Intune Instances** count and link
- **Synced Devices** count
- **Access** link
- **Usage** graph
- **Sync History** table

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune**.

©2026 Tanium Inc. All Rights Reserved

View the Configuration page

About this task

The **Configuration** page for the Tanium Connector for Microsoft Intune shows the following information:

- **Instances** table
- **Role Assignment**: For more information, see User role requirements on page 174.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune**.
3. Click **Configuration**.

View the Tanium Content page

About this task

The **Tanium Content** page for the Tanium Connector for Microsoft Intune shows the following information:

- **Dashboard** summary panes
- **Reports** table

To view the **Tanium Content** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune**.
3. Click **Tanium Content**.

View the Support page

About this task

©2026 Tanium Inc. All Rights Reserved

The **Support** page for the Tanium Connector for Microsoft Intune shows the following information:

- **Create Package** button to create a troubleshooting package for support requests

To view the **Support** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune**.
3. Click **Support**.

View the About page

About this task

The **About** page for the Tanium Connector for Microsoft Intune shows the following information:

- **Extend Visibility**
- **Streamline Reporting**
- **Asset Management**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune**.
3. Click **About**.

Configure integration between Tanium and Microsoft Intune

About this task

Perform the following to ingest mobile device data from Microsoft Intune to Tanium:

1. Understand how Tanium Connector for Microsoft Intune ingests data and functions with Asset. For more information, see Tanium Connector for Microsoft Intune ingestion on page 180.

©2026 Tanium Inc. All Rights Reserved

2. Understand how Tanium Connector for Microsoft Intune functions with Asset. For more information, see Interaction between Asset and Tanium Connector for Microsoft Intune on page 182.
3. In Microsoft Azure, create an application registration, configure the application permissions, and then create an Azure client ID and secret for Tanium Connector for Microsoft Intune to use for authentication. For more information, see Create an Azure client ID and secret on page 183.
4. By default, Tanium Asset views do not include devices managed using Tanium Connector for Microsoft Intune. If you want to include these devices, configure Asset to include devices managed using Tanium Connector for Microsoft Intune. For more information, see (Optional) Include Microsoft Intune devices in Asset views on page 185.
5. Configure a Tanium Connector for Microsoft Intune instance. For more information, see Create a Tanium Connector for Microsoft Intune instance on page 185.

Tanium Connector for Microsoft Intune ingestion

Configure a Tanium Connector for Microsoft Intune instance to connect to a Microsoft Intune instance and ingest mobile device data. Optionally, configure Asset to exclude mobile device data from Asset views.

Each Tanium Connector for Microsoft Intune instance connects to one Microsoft Intune instance in a one-to-one relationship, using the following components:

- The Microsoft Entra tenant ID, used to locate the Microsoft Intune instance
- The Microsoft Intune application (client) ID, used to connect to the Microsoft Intune instance
- Either a client secret or certificate, used to authenticate the connection between Microsoft Intune and the Tanium Connector for Microsoft Intune instance
- A Microsoft Graph endpoint, used to retrieve mobile device data

The Tanium Connector for Microsoft Intune instance fully synchronizes with the Microsoft Intune instance once every eight hours, ingesting all mobile device data into Tanium Core Platform, and incrementally synchronizes only changes to devices once every two minutes. This mobile device data is associated with the following attributes:

- A **Provider Type** of **Microsoft Intune**

©2026 Tanium Inc. All Rights Reserved

- A **Provider Name** of the Tanium Connector for Microsoft Intune instance that ingested the data
- An **Entity Type** of **Mobile Device**

Depending on the number of managed mobile devices in the Microsoft Intune instance, this synchronization might take several minutes or longer. If you retrieve data associated with mobile devices in Tanium Core Platform, such as by issuing a question, the information is accurate as of the synchronization time. Any updates since the synchronization with Microsoft Intune are not reflected in Tanium Core Platform until the next synchronization.

You can apply supported Microsoft Intune remote actions to mobile devices from Tanium Core Platform. If you apply a remote action, the request is sent from Tanium Core Platform to your Microsoft Intune instance, and then the Microsoft Intune instance applies the remote action if possible. For more information, see Microsoft Intune documentation: Device actions.

Note the following:

- Tanium functionality that requires a Tanium Client, such as retrieving certain sensor data, cannot be performed on this mobile device data.
- Because data associated with mobile devices is cached during synchronization, Interact questions that return mobile device data might return the data for mobile devices much faster than for devices managed using Tanium Client, as the Tanium Clients might need time to respond to the question. For example, if you issue a question that targets all entities, the live updates percentage might significantly increase almost immediately as the mobile device data is available, and then increase at a slower rate as Tanium Clients respond.
- If a mobile device is removed from Microsoft Intune, the data is not removed from Tanium Core Platform until the next full synchronization, once every eight hours. The incremental synchronization once every two minutes retrieves mobile device changes, but does not collect mobile device removal. You can view the **Sync History** table on the **Details** page. For more information, see View the Details page on page 177.
- The Tanium Connector for Microsoft Intune instance and mobile devices do not support action approval.
- If you delete a Tanium Connector for Microsoft Intune instance, this action also removes all mobile devices that the deleted instance ingested into Tanium Core Platform. For more information, see Delete a Tanium Connector for Microsoft Intune instance on page 187.

©2026 Tanium Inc. All Rights Reserved

Endpoints managed using an entity provider do not have a Tanium Client installed. Only certain packages can be applied to these endpoints. Package functionality depends on the entity provider type.

Interaction between Asset and Tanium Connector for Microsoft Intune

The Asset custom source for Microsoft Intune ingests data for both mobile devices and other device types from a configured Microsoft Intune instance on a configured schedule. The Tanium Connector for Microsoft Intune ingests data for only mobile devices from a configured Microsoft Intune instance.

> **Note:** Do not configure the Tanium Connector for Microsoft Intune and the Asset custom source for Microsoft Intune at the same time. Configuring both might result in unexpected behavior.

If you configure both the Tanium Connector for Microsoft Intune and the Asset custom source for Microsoft Intune:

- The Tanium Connector for Microsoft Intune synchronizes only mobile device data from Microsoft Intune into Tanium Core Platform.
- The Asset custom source for Microsoft Intune synchronizes data for both mobile devices and other device types from Microsoft Intune into Asset.
    - If you configure the source to perform asset reconciliation, devices must match on both reconciliation keys (`computer_name` and `serial_number`) to be reconciled.
    - Asset reconciliation first checks against the Tanium source in Asset, and then checks against endpoints ingested by the Tanium Connector for Microsoft Intune.

      > **Note:** In this scenario, you cannot configure asset reconciliation to check against only the Tanium source in Asset.

    - If a device managed using Tanium Client or Tanium Connector for Microsoft Intune matches the Tanium source in Asset, the data is merged, and then the data ingested from the Asset custom source for Microsoft Intune is removed.
- The Tanium source in Asset synchronizes all Microsoft Intune mobile device data from Tanium Core Platform into Asset.

©2026 Tanium Inc. All Rights Reserved

- Because the synchronization schedules might not overlap, you might see different update times for devices managed using Tanium Connector for Microsoft Intune versus devices managed using Tanium Client.

If you configure only the Asset custom source for Microsoft Intune:

- The Asset custom source synchronizes data for both mobile devices and other device types from Microsoft Intune into Asset.
    - If you configure the source to perform asset reconciliation, devices must match on both reconciliation keys (`computer_name` and `serial_number`) to be reconciled.
    - Asset reconciliation checks against the Tanium source in Asset.
    - If a device managed using Tanium Client matches a Microsoft Intune device, the data is merged, and then the data ingested from the Asset custom source for Microsoft Intune is removed.
- Tanium Core Platform does not ingest Microsoft Intune device data.

If you configure only the Tanium Connector for Microsoft Intune:

- The Tanium Connector for Microsoft Intune synchronizes only mobile device data from Microsoft Intune into Tanium Core Platform.
- The Microsoft Intune-Mobile Device source in Asset ingests Microsoft Intune device data.
- Tanium Core Platform does not ingest Microsoft Intune data for other device types.

If you configure neither the Asset custom source for Microsoft Intune nor the Tanium Connector for Microsoft Intune, neither Tanium Core Platform nor Asset ingests Microsoft Intune device data.

Create an Azure client ID and secret

About this task

In the Microsoft Azure portal, create an application registration, configure the application permissions, and then create an Azure client ID and secret for Tanium Connector for Microsoft Intune to use for authentication.

For more information, see Microsoft Entra documentation: Quickstart: Register an application with

©2026 Tanium Inc. All Rights Reserved

[the Microsoft identity platform](#).

1. In the Microsoft Azure portal, go to **App registrations** and click **New registration**.
2. Enter a name for the app registration and then select the supported account types. When finished, click **Register**.

   > **Tip:** For more information about registering an application, see Microsoft Entra documentation: Quickstart: Register an application.

3. Record the **Application (client) ID** and **Directory (tenant) ID**.
4. Add a client secret. Go to **Certificates & secrets**, open the **Client secrets** tab, and click **New client secret**. Enter a description and expiration for the secret and then click **Add**.

   > **Tip:** For more information about creating a client secret, see Microsoft Entra documentation: Quickstart: Add a client secret.

5. After you add the client secret, record the **Value** for the client secret and save it to a secure location.

   > **Important:** You cannot see the client secret value again after you leave this page.

6. Add the **DeviceManagementManagedDevices.Read.All** permission to the application registration.

   > **Note:**
   > If you want to send remote actions to Microsoft Intune, also add the **DeviceManagementManagedDevices.ReadWrite.All**, **DeviceManagementConfiguration.ReadWrite.All**, and **DeviceManagementManagedDevices.PrivilegedOperations.All** permissions.
   >
   > If you want to read role scope tags from Microsoft Intune, also add the **DeviceManagementRBAC.Read.All** permission.

   a. From the left-hand navigation menu, go to **API permissions**.
   b. Click **Add a permission**.
   c. Select **Microsoft Graph** > **Application Permissions**.

©2026 Tanium Inc. All Rights Reserved

d. Search for **DeviceManagementManagedDevices**.
e. Select the **DeviceManagementManagedDevices.Read.All** permission and then click **Add Permissions**.
f. The configured API permissions appear with the added **DeviceManagementManagedDevices** permission.
g. Click **Grant admin consent for <your_tenant>**. A message appears to confirm that admin consent is granted to the permissions.

(Optional) Include Microsoft Intune devices in Asset views

About this task

By default, Tanium Asset views do not include devices managed using Tanium Connector for Microsoft Intune. If you want to include these devices, configure Asset to include devices managed using Tanium Connector for Microsoft Intune.

Important: Do not enable this without understanding potential third-party provider and integration costs and limitations. Enabling this includes additional data in an Asset view, which might result in additional bandwidth and storage use, monetary charges, and other related costs.

1. From the Main menu, go to **Modules** > **Asset** > **Overview**, and then click Settings.
2. From the **Advanced** tab, in the **Tanium Entity Providers** section, click to enable **Microsoft Intune-Mobile Device** in addition to any other third-party providers that you want to enable.
3. Click **Save**.

Create a Tanium Connector for Microsoft Intune instance

About this task

Use the Application (client) ID, Directory (tenant) ID, and client secret or certificate PEM file from Microsoft Azure to configure a connection to the Microsoft Intune instance.

Note: Use the **Integration Operator - Microsoft Intune** system role to configure the Tanium Connector for Microsoft Intune instance.

©2026 Tanium Inc. All Rights Reserved

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune** and then click **Configuration**.
3. Click **Add Instance**.
4. Enter a Tanium Connector for Microsoft Intune instance **Name**.
5. Select a **Microsoft Cloud Environment** endpoint to allow communication between the Tanium Connector for Microsoft Intune instance and your Microsoft Intune instance.

   Note: Configure a network allow list rule to allow bidirectional traffic between the Tanium Server and the Microsoft Cloud Environment endpoint over port 443/TCP.
6. Copy your Microsoft Entra tenant GUID and paste it in **Tenant ID**.
7. Enter your Microsoft Intune **Application (Client) ID**.
8. Configure one of the following authentication options:
   a. Select **Secret** authentication, and then enter the **Client Secret**.
   b. Select **Certificate** authentication. Click **Upload Certificate** to upload a certificate PEM file. If the certificate PEM file is password-protected, enter the **Certificate Password**.
9. Assign the Tanium Connector for Microsoft Intune instance configuration to a **Content Set**.
10. To display data from individual devices related to the applications that Intune manages, select **Sync Managed Apps Sensors**. Clear this field to stop synchronizing this data and not display this information for individual devices.
11. To display data from individual devices that might consume additional resources, such as action results, battery details, cellular technology, role scope tags, operating system language, or chassis type, select **Sync Single Device Sensors**. Clear this field to stop synchronizing this data and not display this information for individual devices.
12. To display the configuration policies that apply to an individual device, select **Sync Config Policy Sensors**. Clear this field to stop synchronizing this data and not display this information for individual devices.
13. To display the applications that are installed on an individual device, select **Sync Detected Apps Sensors**. Clear this field to stop synchronizing this data and not display this information for individual devices.
14. To display the compliance policies that apply to an individual device, select **Sync**

©2026 Tanium Inc. All Rights Reserved

Compliance Policy Sensors. Clear this field to stop synchronizing this data and not display this information for individual devices.

> **Note:** If you enable **Sync Detected Apps**, **Sync Config Policy Sensors**, or **Sync Compliance Policy Sensors**, this synchronization occurs once every 72 hours. Individual devices synchronize at a random time during each 72 hour interval.

15. To synchronize only corporate devices, and not personal devices monitored by the Microsoft Intune instance, select **Sync Company Owned Devices Only**.
16. Click **Verify Connection** to test the connection settings. If the connection cannot be established, check the Microsoft Intune configuration and the Tanium Connector for Microsoft Intune instance configuration settings, and then try again.
17. Click **Create**.

Edit a Tanium Connector for Microsoft Intune instance

About this task

Edit a Tanium Connector for Microsoft Intune instance to update the display **Name**, **Content Set**, and the **Authentication** method, including the **Client Secret** or **Certificate**. Update the instance if you need to update the authentication, such as for rotating a certificate, or if you want to update the content set to change or restrict Tanium operator access to the instance.

After you create a Tanium Connector for Microsoft Intune instance, you cannot update the **Microsoft Cloud Environment** endpoint, **Tenant Name**, **Tenant ID**, or **Application (Client) ID**. If you want to change these values, delete the existing Tanium Connector for Microsoft Intune instance and then create a new one.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune** and then click **Configuration**
3. Click Edit Instance .
4. Configure the settings for the Tanium Connector for Microsoft Intune instance.
5. Click **Save**.

Delete a Tanium Connector for Microsoft Intune instance

©2026 Tanium Inc. All Rights Reserved

About this task

Deleting a Tanium Connector for Microsoft Intune instance also removes all Microsoft Intune mobile device data that this entity provider ingested. Delete the instance if you want to stop managing Microsoft Intune mobile device data in Tanium Console.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune** and then click **Configuration**
3. Click Delete Instance for the Tanium Connector for Microsoft Intune instance that you want to delete.

Monitor Tanium Connector for Microsoft Intune

View Tanium Connector for Microsoft Intune instances

About this task

To view the Tanium Connector for Microsoft Intune instances:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune**.
3. Click **Configuration**.

Filter Tanium Connector for Microsoft Intune instance list

About this task

You can filter or order the list of Tanium Connector for Microsoft Intune instances.

- To filter for a specific instance, enter a string value in the **Filter items** field. The list updates with any instances that contain the value you entered. To clear the filter, click **X** in the **Filter items** field.
- To filter for a specific field value, enter a string value in the **Tenant ID Name**, **Tenant ID Value**, **Application (Client) ID**, or **Content Set** filter fields.
- Click a column header to sort the instances by the data in the column in descending order.

©2026 Tanium Inc. All Rights Reserved

Click the column header again to sort the list in ascending order. To clear the sort, click the column header a third time.

Use Tanium Connector for Microsoft Intune mobile devices and data

Issue questions to target Microsoft Intune mobile devices

> **Note:**
>
> The **Provider Type** value for Google devices differs based on the entity provider:
>
> - Devices ingested using the Endpoint Management for Mobile entity provider have a **Provider Type** of **Device Management Google**.
> - Devices ingested using the Tanium Connector for Microsoft Intune entity provider have a **Provider Type** of **Microsoft Intune**.

FILTER ENTITIES BY PROVIDER IN INTERACT QUESTIONS

You can use the **Provider Type**, **Provider Name**, and **Entity Type** sensors to return results from certain types of managed endpoints, such as endpoints managed using Tanium Client or endpoints managed using Tanium Connector for Microsoft Intune.

Entity providers and related sensor values

Entity Provider	Provider Type value	Provider Name value	Entity Type value
Tanium Client	Tanium Client	Tanium	Computer
Tanium Connector for Microsoft Intune	Microsoft Intune	<configured-entity-provider-name>	Mobile Device

The following question returns all mobile devices, such as those ingested by the Tanium Connector for Microsoft Intune entity provider:

```
Get Computer Name and Provider Name and Provider Type and Entity Type from all entities with
```

©2026 Tanium Inc. All Rights Reserved

```
Entity Type equals Mobile Device
```

The following question returns all computers or workstations, such as those managed by Tanium Client:

```
Get Computer Name and Provider Name and Provider Type and Entity Type from all entities with Entity Type equals Computer
```

The following question returns all mobile devices ingested by Tanium Connector for Microsoft Intune:

```
Get Computer Name and Provider Name and Provider Type and Entity Type from all entities with Provider Type equals Microsoft Intune
```

The following questions returns all devices managed using Tanium Client:

```
Get Computer Name and Provider Name and Provider Type and Entity Type from all entities with Provider Type equals Tanium Client
```

```
Get Computer Name and Provider Name and Provider Type and Entity Type from all entities with Provider Name equals Tanium
```

The following question returns all mobile devices ingested by the Tanium Connector for Microsoft Intune instance named `Example Connector for Microsoft Intune`:

```
Get Computer Name and Provider Name and Provider Type and Entity Type from all entities with Provider Name equals Example Connector for Microsoft Intune
```

Run a remote action on a mobile device

About this task

You can send a Microsoft Intune remote action request from the Endpoint Details page for a mobile device. The Tanium Connector for Microsoft Intune attempts to send a remote action to the Microsoft Intune instance for up to ten minutes. The **Sent to Microsoft Intune** status, available in the Action History tab, updates to one of several statuses:

- **Pending Send**: The Tanium Connector for Microsoft Intune is attempting to send the remote action to the Microsoft Intune instance.
- **Send Failed**: The remote action failed to send after ten minutes of attempts.
- **Sent**: The Microsoft Intune instance received the action. The Microsoft Intune instance then attempts to apply the remote action to the managed mobile device.

©2026 Tanium Inc. All Rights Reserved

Note: If you configure a **Device actions** access policy in the Microsoft Intune admin center, and the policy has Microsoft Intune Multi Admin Approval (MAA) enabled, **Wipe Device** and **Retire Device** remote actions from Tanium fail with a **Send Failed** status. The Tanium Connector for Microsoft Intune does not support action approval, and does not send approval headers required by MAA. If you want to enable sending these remote actions from Tanium, exclude the app registration for this integration from the **Device actions** access policy. For more information, see Wipe Device or Retire Device remote actions fail if Multi Admin Approval is enabled on page 196.

Deploy simple actions and ring deployments using Console

You can use Tanium Console to target endpoints managed using an entity provider with a simple action or deployment plan. For more information, see Tanium Console User Guide: Managing scheduled actions and action history and Tanium Console User Guide: Deploying actions and playbooks in Console and Interact.

Deploy actions using an Automate playbook

You can use Tanium Automate to target endpoints managed using an entity provider in an Automate playbook with a Deploy Action step. For more information, see Tanium Automate User Guide: Deploy Action step and Tanium Automate User Guide: Create a playbook.

1. Open the Endpoint Details page for a mobile device. For more information, see Tanium Reporting User Guide: View endpoint details.

2. Select a Deploy Action option for the desired remote action.

MICROSOFT INTUNE REMOTE ACTIONS

Deploy a Microsoft Intune remote action to a mobile device managed by Microsoft Intune by selecting a **Deploy Action** option at the top of the page. The available remote actions vary by endpoint OS. For more information, see Microsoft Intune documentation: Use remote actions to manage devices using Microsoft Intune.

©2026 Tanium Inc. All Rights Reserved

Note:

Viewing Microsoft Intune remote actions requires the **Action read** platform content permission on the **Mobile** content set for actions that do not have a high impact, and the **Action read** platform content permission on the **Mobile - High Impact** content set for the **Lost Mode**, **Retire Device**, and **Wipe Device** remote actions. The **Mobile Reader**, **Mobile Action User** and **Mobile High Impact Action User** system roles have these permissions.

Deploying Microsoft Intune remote actions that do not have a high impact requires the **Action write** platform content permission on the **Mobile** content set. The **Mobile Action User** and **Mobile High Impact Action User** system roles have this permission.

Deploying a **Lost Mode**, **Retire Device**, or **Wipe Device** remote action requires the **Action write** platform content permission on the **Mobile - High Impact** content set. The **Mobile High Impact Action User** system role has this permission.

Note: Microsoft Intune remote action requests are sent to the Microsoft Intune instance, which then attempts to apply the remote action to the mobile device. This might take several minutes.

Action	Operating System	Description
Disable Activation Lock	iOS, iPadOS	Remove the Activation Lock, which associates a device with an Apple ID and password. For more information, see Microsoft Intune documentation: Device action: disable Activation Lock .
Lost Mode	iOS, iPadOS	Lock a device, show a custom message, and disable sound and vibration. • Select whether to **Enable** or **Disable** Lost Mode. • If you enable Lost Mode, enter a **Message to display on lock screen**, **Phone number to display on lock screen**, and **Footer message to display on lock screen**. For more information, see Microsoft Intune documentation: Device action: Lost Mode .
Remote Lock	Android, iOS, iPadOS	Lock a device and reset the device passcode. For more information, see Microsoft Intune documentation: Device action: remote lock .

©2026 Tanium Inc. All Rights Reserved

Action	Operating System	Description
Reset Passcode	Android, iOS, iPadOS	Reset the device passcode. For more information, see Microsoft Intune documentation: Device action: reset passcode .
Restart Device	Android, iOS, iPadOS	Restart the device. For more information, see Microsoft Intune documentation: Device action: restart .
Retire Device	Android, iOS, iPadOS	Remove company data and settings from a device, and leave personal data intact. For more information, see Microsoft Intune documentation: retire . **Note:** If you configure a **Device actions** access policy in the Microsoft Intune admin center, and the policy has Microsoft Intune Multi Admin Approval (MAA) enabled, this action returns a **Send Failed** status and the remote action is not applied. For more information, see Wipe Device or Retire Device remote actions fail if Multi Admin Approval is enabled on page 196 .
Send Custom Notification	Android, iOS, iPadOS	Send a custom notification to a device. • Enter a **Notification Title** and **Notification Body**. For more information, see Microsoft Intune documentation: Device action: send custom notification .
Synchronize Device	Android, iOS, iPadOS	Synchronize a device with Microsoft Intune to apply the latest policies and configuration. For more information, see Microsoft Intune documentation: Device action: sync .
Wipe Device	Android, iOS, iPadOS	Restore a device to factory default settings. • For iOS devices, select whether to **Preserve cellular data plan for eSIM device**. For more information, see Microsoft Intune documentation: wipe . **Note:** If you configure a **Device actions** access policy in the Microsoft Intune admin center, and the policy has Microsoft Intune Multi Admin Approval (MAA) enabled, this action returns a **Send Failed** status and the remote action is not applied. For more information, see Wipe Device or Retire Device remote actions fail if Multi Admin Approval is enabled on page 196 .

Include Microsoft Intune mobile devices in a report

About this task

©2026 Tanium Inc. All Rights Reserved

When you work in the **Explore Data** page or edit a report, the **Source Data** panel lists all registered sensors, along with certain sources of data that are not present on endpoints (for more information, see Tanium Reporting User Guide: Registered sensors). You use the panel to add data sources as columns to the grid in the page or report. Each column lists the results that endpoints returned for the corresponding sensor or lists the values that Tanium solutions calculated for other data sources. If a single source produces multiple columns of results, the column headings show the source name above the column names.

1. Perform one of the following steps based on whether you plan to edit an existing report or create a new view of endpoint data that you might or might not save as a report.
    - Existing report: Open the report and click **Edit Data**.
    - New view or report: From the Main menu, go to **Data** > **Explore Data**.

    Tip: You can also access the **Explore Data** page from the following locations:

    - An existing report: Click **New Report** or, in a non-editable report, click **Explore Data**.
    - The **Data** > **Reports** page: Click **Create Report**.

2. Select a Data Source to limit the results to endpoints managed using Tanium Client or an entity provider, or select All Entities to return results from all endpoints.

    Note: Select Save as default to save your current Data Source selection for future reports.

3. Configure the report. For more information, see Tanium Reporting User Guide: Explore data and create reports.

    Note: If you select **Microsoft Intune** or **All Endpoints** as the **Data Source**, you can filter results to show only endpoints running the iOS or Android operating system.

Export Microsoft Intune mobile device data using Tanium Connect

If the connection source supports Microsoft Intune mobile device data, such as the **Tanium Reporting (Source Data)** source, you can export this data using Tanium Connect. For more

©2026 Tanium Inc. All Rights Reserved

information, see Tanium Connect User Guide: Overview.

Troubleshooting

If the Tanium Connector for Microsoft Intune is not performing as expected, you might need to troubleshoot issues or change settings.

Collect logs

About this task

The information is saved as a ZIP file that you can download with your browser. The ZIP file is also known as a support bundle.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Microsoft Intune**.
3. Click **Support**.
4. Click **Create Package**. An integrations-gallery-support-bundle.[timestamp].zip file downloads to the local download directory.
5. Contact Tanium Support to determine the best option to send the ZIP file. For more information, see View the Support page on page 178.

Cannot establish connection between Tanium and Microsoft Intune

If the Tanium Connector for Microsoft Intune cannot establish a connection with Microsoft Intune, verify that all IDs match the Microsoft Intune settings, and that the network traffic is allowed.

- Verify that the **Tenant ID** and **Application (Client) ID** values match the Intune app registration values.
- Verify that you selected the intended Microsoft Cloud Environment endpoint.
- Configure a network allow list rule to allow bidirectional traffic between the Tanium Server and the Microsoft Cloud Environment endpoint over port 443/TCP.
- Ensure that no network block list rules block traffic to the Microsoft Cloud Environment endpoint. If a network block list rule identifies a CIDR range or uses wildcards to identify

©2026 Tanium Inc. All Rights Reserved

URLs, and includes the Microsoft Cloud Environment endpoint, either create an exception or adjust the evaluation priority to allow this traffic.

Cannot authenticate to Microsoft Intune

If the provided Microsoft Intune credentials do not allow authentication to the Microsoft Intune instance, verify that the credentials are in the correct format:

- If you entered a **Client Secret**, verify that the value matches the value in the Microsoft Intune app registration.
- If you uploaded a public key **Certificate**, verify that the certificate is in PEM format and well-formed, and if required, that the certificate **Password** value matches the password needed to access the certificate.

Cannot access a route, or retrieve groups or devices, or Microsoft Intune permissions are missing

If Microsoft Intune content cannot be accessed or retrieved, verify that the correct Microsoft Intune permissions are assigned to the Microsoft Intune app registration.

Microsoft Intune app registration permission scope	Description
DeviceManagementManagedDevices.Read.All	Read Microsoft Intune device data and ingest device data into Tanium Core Platform
DeviceManagementConfiguration.ReadWrite.All	Read Microsoft Intune device configuration and policies and apply remote actions from Tanium Core Platform
DeviceManagementManagedDevices.ReadWrite.All	Read Microsoft Intune device data and apply remote actions from Tanium Core Platform
DeviceManagementManagedDevices.PrivilegedOperations.All	Apply user-impacting remote actions from Tanium Core Platform
DeviceManagementRBAC.Read.All	Read Microsoft Intune role scope tags

Wipe Device or Retire Device remote actions fail if Multi Admin Approval is enabled

©2026 Tanium Inc. All Rights Reserved

About this task

If you configure a **Device actions** access policy in the Microsoft Intune admin center, and the policy has Microsoft Intune Multi Admin Approval (MAA) enabled, **Wipe Device** and **Retire Device** remote actions from Tanium return a **Send Failed** status and the remote action is not applied to the targeted device. The Tanium Connector for Microsoft Intune does not support action approval, and does not send approval headers required by MAA.

If you want to enable sending these remote actions from Tanium, exclude the app registration for this integration from the **Device actions** access policy. As part of MAA, a second admin must approve the exclusion before it takes effect.

> **Note:** If you exclude the app registration, **Wipe Device** and **Retire Device** remote actions that you send from Tanium are not subject to the second-admin approval requirement that MAA enforces. For more information, see Microsoft Intune documentation: Exclude an application from MAA enforcement.

Android, ChromeOS, and Google are trademarks of Google LLC.

Managing the Tanium Security Browser Connector for Microsoft Edge for Business

Important:

To use the Tanium Security Browser Connector for Microsoft Edge for Business, you must be a:

- Microsoft 365 and Microsoft Intune subscriber
- Tanium on-premises customer

For more information about Microsoft Edge for Business, see Microsoft Edge Enterprise documentation: Microsoft Edge for Business.

The Tanium Security Browser Connector for Microsoft Edge for Business (Security Browser Connector) ingests browser use metrics and related data from Windows endpoints running Microsoft Edge for Business. Using Tanium Console, you can:

- Generate reports that contain this data, and better analyze possible malicious browser behavior
- Identify suspicious endpoints from the report data
- Further investigate endpoints and any behavior related to the reporting metrics

Before you begin

- You must have a Microsoft 365 subscription that includes Microsoft Entra ID and Microsoft Edge.
    - Microsoft 365 requires a license. For more information, see Microsoft 365

©2026 Tanium Inc. All Rights Reserved

documentation: Microsoft 365 and Office 365 plan options.

- You must have at least one Windows endpoint that runs Microsoft Edge for Business. For more information about deploying Microsoft Edge, see Microsoft Edge Enterprise documentation: Plan your deployment of Microsoft Edge.
- Each endpoint must have a unique device ID.

  Important: Due to how Microsoft Azure creates virtual machines, multiple virtual machines that run Windows 10 or later might be assigned non-unique device IDs. All virtual machines with the same non-unique device ID are recognized as a single virtual machine in Tanium Data Service. Microsoft Edge for Business browser data from multiple virtual machines might not appear properly in reports and dashboards. For more information about how to assign unique device IDs, see Cannot properly view browser use data from multiple endpoints on page 220.

- You must satisfy Microsoft Edge for Business security connector prerequisites. For more information, see Microsoft Edge Enterprise documentation: Prerequisites.
- You must have at least one Microsoft Entra security group with at least one user. Add users whose browser activity you want to track. For more information, see Microsoft Entra documentation: Manage Microsoft Entra groups and group membership.

- You must have a Microsoft Intune subscription. There must be at least one enrolled device that runs both Microsoft Edge for Business and Windows 10 or later.
  - Microsoft Intune requires a license. For more information, see Microsoft Intune documentation: Microsoft Intune licensing.
  - The Tanium Security Browser Connector for Microsoft Edge for Business supports devices that run Microsoft Windows 10 or later. For more information, see Microsoft Intune documentation: Enrollment guide: Enroll Windows client devices in Microsoft Intune.
- The Tanium Security Browser Connector for Microsoft Edge for Business does not require adding specific URLs to your network allow list. However, ensure that you add required URLs to your network allow list for Microsoft Edge to function properly. For more information, see Microsoft Edge documentation: Allow list for Microsoft Edge endpoints.


©2026 Tanium Inc. All Rights Reserved

Architecture

The Microsoft Edge management service collects and collates browser use data and metrics from the Microsoft Edge for Business browser instances that run on Windows endpoints. Microsoft Intune manages these endpoints. The Microsoft Edge management service send this browser use data and metrics to the configure Tanium environment. The Tanium Security Browser Connector for Microsoft Edge for Business, using Tanium Asset, ingests this data. This data is cached in Tanium Core Platform.

Tanium operators can include this browser data in Tanium Reporting reports and dashboards, or export the data using Tanium Connect.

Figure 4. Example Tanium Security Browser Connector for Microsoft Edge for Business architecture



Requirements

Review the requirements before you install and use the Tanium Security Browser Connector for Microsoft Edge for Business.

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium license that includes an Endpoint Management Standard or Endpoint Management Plus bundle. For more information about how to get an Endpoint Management bundle and Tanium Security Browser Connector for Microsoft Edge for Business, see Tanium Solutions & Bundles.
- Tanium™ Core Platform servers
- Tanium™ Client: No client requirements.

©2026 Tanium Inc. All Rights Reserved

> **Note:** The Tanium Security Browser Connector for Microsoft Edge for Business dashboards show information only for endpoints that run Tanium Client. For more information, see View Tanium Security Browser Connector for Microsoft Edge for Business reports and dashboards on page 217.

- Tanium™ Console

Solution dependencies

Other Tanium solutions are required for the Tanium Security Browser Connector for Microsoft Edge for Business to function (required dependencies) or for specific Tanium Security Browser Connector for Microsoft Edge for Business features to work (feature-specific dependencies). The installation method that you select determines if the Tanium Server automatically imports dependencies or if you must manually import them.

> **Note:** Some Tanium Security Browser Connector for Microsoft Edge for Business dependencies have their own dependencies, which you can see by clicking the links in the lists of Required dependencies on page 201 and Feature-specific dependencies on page 201. Note that the links open the user guides for the latest version of each solution.

REQUIRED DEPENDENCIES

The Tanium Security Browser Connector for Microsoft Edge for Business has the following required dependencies:

- Tanium™ Asset
- Tanium™ Partner Integration
- Tanium™ Reporting

FEATURE-SPECIFIC DEPENDENCIES

The Tanium Security Browser Connector for Microsoft Edge for Business has the following feature-specific dependencies:

©2026 Tanium Inc. All Rights Reserved

- Tanium™ Automate to take actions from a dashboard related to Automate
- Tanium™ Criticality to view dashboard information related to endpoint criticality and risk score
- Tanium™ Enforce to take actions from a dashboard related to Enforce
- Tanium™ Performance to view the dashboard overview and information related to browser performance
- Tanium™ Threat Response to take actions from a dashboard related to Threat Response

Endpoints

Supported Internet protocols

The Tanium Security Browser Connector for Microsoft Edge for Business supports IPv4 and IPv6 addresses.

Supported operating systems

The following endpoint operating systems are supported with the Tanium Security Browser Connector for Microsoft Edge for Business.

- Windows 10 or later

For more information about supported Windows operating system versions, see Microsoft Edge Enterprise documentation: Microsoft Edge supported Operating Systems.

The Tanium Security Browser Connector for Microsoft Edge for Business does not install the Tanium Client or deploy packages to endpoints. For more information about Tanium Client operating system support, see Tanium Client Management User Guide: Client version and host system requirements.

Third-party software

You must have a Microsoft 365 subscription that includes Microsoft Entra ID, Microsoft Edge for Business, and Microsoft Intune. For more information, see Before you begin on page 198.

Host and network security requirements

©2026 Tanium Inc. All Rights Reserved

Specific ports and processes are needed to run the Tanium Security Browser Connector for Microsoft Edge for Business.

Ports

No ports are required for Tanium Security Browser Connector for Microsoft Edge for Business communication.

For more information about Tanium Cloud ports, see Host and network security requirements.

SECURITY EXCLUSIONS

If antivirus (AV) or other security software is in use in the environment to monitor and block unknown host system processes, Tanium requires that a security administrator create exclusions to allow the Tanium processes to run without interference. This software can include security applications that are included with an endpoint operating system, such as fapolicyd on some Linux distributions, or Microsoft Defender on Windows. The configuration of these exclusions varies depending on the security software.

No additional security exclusions are required.

User role and persona requirements

Important: Assign the **Asset API User** system role to your user account to generate an API token. The first time that you generate an API token for the Tanium Security Browser Connector for Microsoft Edge for Business, the system automatically creates the **Microsoft Edge for Business API User** system persona and assigns the **Asset Microsoft Edge for Business API User** system role. Do not assign this persona to a user, as it is used for API tokens. Do not delete this persona, as the Tanium Security Browser Connector for Microsoft Edge for Business requires this persona.

The **Microsoft Edge for Business API User** persona is required to configure the Security Browser Connector for Microsoft Edge for Business integration. The assigned **Asset Microsoft Edge for Business API User** system role allows API token authentication for this integration. For more information on personas, see Tanium Console User Guide: Managing personas.

Predefined roles grant the following permissions, which are required to use Microsoft Edge for Business integration functionality:

©2026 Tanium Inc. All Rights Reserved

- Table 45. Security Browser Connector for Microsoft Edge for Business solution permissions on page 204
- Table 46. Asset solution permissions on page 205
- Table 47. Security Browser Connector for Microsoft Edge for Business administration and platform content permissions on page 206: The solution permissions automatically provide some of these permissions.
- Table 48. Asset administration and platform content permissions on page 206: The solution permissions automatically provide some of these permissions.

Some Microsoft Edge for Business integration solution permissions provide permissions that are associated with other solutions. Furthermore, all the platform content permissions and some solution permissions apply to content sets that might contain content for other solutions in addition to the Microsoft Edge for Business integration. If you create custom roles for Microsoft Edge for Business integration users, be sure to assign all the solution permissions and content set permissions that are required for Microsoft Edge for Business integration functionality. If you are not sure which permissions are required for a custom role, view the permissions of the predefined roles. For more information, see the following sections of the Tanium Console User Guide:

- RBAC overview (provides an overview of roles, permissions, and content sets)
- Provided role permissions
- View effective role permissions
- Configure a custom role

Security Browser Connector for Microsoft Edge for Business solution permissions

Permission	Integration Operator - Microsoft Edge for Business [1]	Integration Viewer - Microsoft Edge for Business [1]
Partner Integration Access Integrations Gallery	✓ SHOW	✓ SHOW
Partner Integration API Use the Partner Integration API	✓	✓

Permission	Integration Operator - Microsoft Edge for Business [1]	Integration Viewer - Microsoft Edge for Business [1]
	EXECUTE	EXECUTE
Partner Integration Credentials Access Partner Integration credentials	✓ READ WRITE DELETE	✓ READ
Partner Integration Gallery View the Integrations Gallery	✓ READ	✓ READ
Partner Integration Gallery Microsoft Edge for Business View Security Browser Connector for Microsoft Edge for Business in Integrations Gallery	✓ READ WRITE	✓ READ
Partner Integration Reporting Metrics View metrics information in Integrations Gallery	✓ READ	✓ READ

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

Asset solution permissions

Permission	Asset Microsoft Edge for Business API User [1]
Asset Microsoft Edge Events Queue Microsoft Edge events	✓ QUEUE

[1] The permissions for this role provide solution permissions for other solutions. To view the provided permissions, see View effective role permissions .

©2026 Tanium Inc. All Rights Reserved

Security Browser Connector for Microsoft Edge for Business administration and platform content permissions

Permission	Permission Type	Integration Operator - Microsoft Edge for Business	Integration Viewer - Microsoft Edge for Business
Action Group	Administration	✓ READ	✓ READ
Filter Group	Platform Content	✓ READ	✓ READ
Package	Platform Content	✓ READ	✓ READ
Plugin	Platform Content	✓ READ EXECUTE	✓ READ EXECUTE
Sensor	Platform Content	✓ READ	✓ READ

To view the content sets to which the platform content permissions apply, see View effective role permissions .

Asset administration and platform content permissions

Permission	Permission Type	Asset Microsoft Edge for Business API User
Plugin	Platform Content	✓ READ EXECUTE

To view the content sets to which the platform content permissions apply, see View effective role permissions .

View the Details page

About this task

©2026 Tanium Inc. All Rights Reserved

The **Details** page for the Tanium Security Browser Connector for Microsoft Edge for Business shows the following information:

- **Service Enablement** toggle
- **Microsoft 365 Console** link
- **Usage** dashboard

To view the **Details** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.

View the Configuration page

About this task

The **Configuration** page for the Tanium Security Browser Connector for Microsoft Edge for Business shows the following information:

- **Register Tanium with Microsoft Edge for Business** configuration settings
- **Role Assignment**: For more information, see User role and persona requirements on page 203.

To view the **Configuration** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **Configuration**.

View the Tanium Content page

About this task

©2026 Tanium Inc. All Rights Reserved

The **Tanium Content** page for the Tanium Security Browser Connector for Microsoft Edge for Business shows the following information:

- **Dashboard** summary panes
- **Reports** table

To view the **Tanium Content** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **Tanium Content**.

View the Support page

About this task

The **Support** page for the Tanium Security Browser Connector for Microsoft Edge for Business shows the following information:

- **Create Package** button to create a troubleshooting package for support requests

To view the **Support** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **Support**.

View the About page

About this task

The **About** page for the Tanium Security Browser Connector for Microsoft Edge for Business shows the following information:

- **Collection of Browser Data**

©2026 Tanium Inc. All Rights Reserved

- **Login Tracking**
- **Sensitive Data Transfer**
- **Reports and Alerts**

To view the **About** page:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **About**.

Configure Tanium Security Browser Connector for Microsoft Edge for Business

About this task

Perform the following high-level tasks to ingest Microsoft Edge for Business browser data into Tanium:

1. Configure a Microsoft Edge for Business configuration policy for Microsoft Intune, assigning Microsoft Entra security groups or all users in the Microsoft Entra tenant. For more information about configuration steps, see Create a Microsoft Edge for Business configuration policy on page 209.
2. Enable the Tanium Security Browser Connector for Microsoft Edge for Business integration. For more information about configuration steps, see Enable the Tanium Security Browser Connector for Microsoft Edge for Business integration on page 211.
3. Configure the Tanium Security Browser Connector for Microsoft Edge for Business. Copy the URL for communication between Tanium and the Microsoft Entra tenant and generate an API token for authentication from the Microsoft Entra tenant to Tanium. Use this information to configure the Tanium reporting connector from the Microsoft 365 admin center. For more information about configuration steps, see Configure the Tanium Security Browser Connector for Microsoft Edge for Business on page 211.

Create a Microsoft Edge for Business configuration policy

©2026 Tanium Inc. All Rights Reserved

About this task

Create a Microsoft Edge for Business configuration policy for Microsoft Intune that you use to determine the scope of Windows endpoint browser data that is sent to the Tanium Security Browser Connector for Microsoft Edge for Business. You can configure Microsoft Entra security groups to target.

Note: The Tanium Security Browser Connector for Microsoft Edge for Business requires the `OnSecurityEventEnterpriseConnector` setting, which is automatically added after you create the configuration policy. This integration does not require additional settings or extensions in the configuration policy. You can configure additional settings and extensions as required by your organization.

Note: Microsoft Edge for Business configuration policies for Microsoft Intune do not have priority. If more than one Microsoft Intune configuration policy applies to a user, conflicting settings do not automatically resolve. Review existing configuration policies for settings that might conflict with this configuration policy and resolve any conflicts before creating this configuration policy. For more information, see Microsoft Edge Enterprise documentation: Get started with configuration policies.

1. In a browser window, go to the Microsoft 365 admin center and sign in.
2. From the Main menu, go to **Settings** > **Microsoft Edge**.
3. Click **Configuration policies**.
4. Click **Create policy**.
   The Create a configuration policy for Microsoft Edge wizard appears.
5. Enter a configuration policy **Name**, such as `tanium-edge-browser-configuration-example`.
6. Enter an optional description, such as `Tanium Security Browser Connector for Edge for Business`.
7. Select **Windows 10+** and clear **macOS 11+**, **iOS**, and **Android**.
8. Select a **Policy type** of **Intune**.

©2026 Tanium Inc. All Rights Reserved

9. Click **Next**.
   The Settings page appears.
10. If you want to configure additional settings, click **Add setting** and configure the settings.
11. Click **Next**.
    The Extensions page appears.
12. If you want to configure additional extensions, configure the extensions and then click **Next**.
    The Assignments page appears.
13. Assign Microsoft Entra security groups to this configuration policy. Click **Select group** and assign one or more security groups.
14. Click **Next**.
    The Finish page appears.
15. Review the configuration policy settings and then click **Review and create**.

Enable the Tanium Security Browser Connector for Microsoft Edge for Business integration

About this task

Note: Use the **Integration Operator - Microsoft Edge for Business** system role to enable the Tanium Security Browser Connector for Microsoft Edge for Business integration.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **Enable** and then confirm your selection.

Configure the Tanium Security Browser Connector for Microsoft Edge for Business

About this task

Establish communication between a Tanium instance and Microsoft 365 instance using:

©2026 Tanium Inc. All Rights Reserved

- a URL to a Tanium instance to connect Microsoft 365 to the Tanium instance and pass Microsoft Edge for Business browser use data
- a Tanium API token to grant Microsoft 365 permission to send Microsoft Edge for Business browser use data

Important: Assign the **Asset API User** system role to your user account to generate an API token. The first time that you generate an API token for the Tanium Security Browser Connector for Microsoft Edge for Business, the system automatically creates the **Microsoft Edge for Business API User** system persona and assigns the **Asset Microsoft Edge for Business API User** system role. Do not assign this persona to a user, as it is used for API tokens. Do not delete this persona, as the Tanium Security Browser Connector for Microsoft Edge for Business requires this persona.

Note: Use the **Asset API User** and **Integration Operator - Microsoft Edge for Business** or **Integration Operator - Microsoft Edge for Business** system roles to configure the Tanium Security Browser Connector for Microsoft Edge for Business.

1. In a browser window, go to the Microsoft 365 admin center and sign in.
2. From the Main menu, go to **Settings** > **Microsoft Edge**.
3. Click **Connectors**.
4. In the Tanium pane, click **Set up**.
5. Select the configuration policy that you configured for the Tanium Security Browser Connector for Microsoft Edge for Business.
6. In a separate browser window, go to Tanium Console and sign in.
7. From the Main menu, go to **Shared Services** > **Integrations Gallery** and then click **Tanium Security Browser Connector for Microsoft Edge for Business**.
8. Go to the **Configuration** tab.
9. Click **Tanium Instance URL** Copy to copy the Tanium instance URL to the clipboard.
10. In the Microsoft 365 admin center, paste the **Tanium Instance URL** in the **URL required** field.
11. Enter `443` in the **Port** field.

©2026 Tanium Inc. All Rights Reserved

12. Select whether to allow connections from trusted Microsoft services or manually enter trusted IP addresses:
    - Select **Allow connections from trusted Microsoft 365 endpoints** and then select the **Microsoft Cloud Environment** that matches your organization. Tanium populates the trusted IP address allow list from the Microsoft 365 published endpoint list and periodically retrieves updates from this list to keep the allow list current.

      > **Note:** If the trusted IP address allow list associated with your API token drifts from the current Microsoft 365 published endpoint list, Tanium displays a banner with the option to rotate the token. For more information, see Rotate the Tanium Security Browser Connector for Microsoft Edge for Business API token on page 214.

    - Clear **Allow connections from trusted Microsoft 365 endpoints** to manually enter **Custom Trusted IP Addresses** to associate with the API token.

13. Click **Generate** to generate an API token and copy the token value to the clipboard. This API token is associated with the user account creating the token, contains `Microsoft Edge for Business` in the **Notes** field, and is valid for 30 days from generation.

    > **Note:** You cannot view the token value in Tanium Console. Paste the value in a plaintext editor and save the file in a secure location if you want to record it for future reference.

    > **Note:**
    > Do not use a single token for multiple processes. For example, do not use:
    >
    > - A single token for a ServiceNow integration and a Splunk integration
    > - A single token for multiple ServiceNow instances
    > - A single token or multiple connections from one ServiceNow instance to Tanium Cloudthe Tanium Server.
    >
    > When a token rotates for any process, that token stops working for any other processes that use it.

14. In the Microsoft 365 admin center, paste the API token value in the **API Key** field.

©2026 Tanium Inc. All Rights Reserved

15. Click **Test Connection**. If the connection cannot be established, check settings and try again.
16. Select the events to send to Tanium.

    Note: Certain event types might have additional requirements before you can retrieve them.

17. Click **Save configuration**.

Manage the Tanium Security Browser Connector for Microsoft Edge for Business

View Tanium Security Browser Connector for Microsoft Edge for Business configuration

About this task

To view the Tanium Security Browser Connector for Microsoft Edge for Business configuration:

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **Configuration**.

Rotate the Tanium Security Browser Connector for Microsoft Edge for Business API token

About this task

The API token that you generate for the Tanium Security Browser Connector for Microsoft Edge for Business is valid for 30 days from generation. You can manually rotate API this token within that 30 day expiration, which automatically revokes the existing token and generates a new token, then upload the new API token value to the Tanium reporting connector configuration in the Microsoft 365 admin center. This new token is automatically associated with the **Microsoft Edge for Business API User** system persona.

©2026 Tanium Inc. All Rights Reserved

Note: Assign the **Asset API User** system role to your user account to rotate an API token.

Note: You cannot view the token value in Tanium Console. Paste the value in a plaintext editor and save the file in a secure location if you want to record it for future reference.

Note: Do not use a single token for multiple processes. For example, do not use a single token for a ServiceNow integration and a Splunk integration, or for multiple ServiceNow instances, or for multiple connections from one ServiceNow instance to Tanium Cloudthe Tanium Server. When a token rotates for any process, that token stops working for any other processes that use it.

1. In a browser window, go to the Microsoft 365 admin center and sign in.
2. From the Main menu, go to **Settings** > **Microsoft Edge**.
3. Click **Connectors**.
4. In the Tanium pane, click **Set up**.
5. In a separate browser window, go to Tanium Console and sign in.
6. From the Main menu, go to **Shared Services** > **Integrations Gallery** and then click **Tanium Security Browser Connector for Microsoft Edge for Business**.
7. Go to the **Configuration** tab.
8. Click **Rotate**.
   The existing API token that is associated with this integration is revoked. The new API token is copied to the clipboard.
9. In the Microsoft 365 admin center, paste the API token value in the **API Key** field.
10. Click **Test Connection**. If the connection cannot be established, check settings and try again.
11. Click **Save configuration**.

Revoke the Tanium Security Browser Connector for Microsoft Edge for Business API token

©2026 Tanium Inc. All Rights Reserved

About this task

You can manually revoke the API token that you associate with the Tanium Security Browser Connector for Microsoft Edge for Business. If you revoke the token, the **Microsoft Edge for Business API User** system persona is automatically deleted. Revoke an API token for security-related reasons, or if you want to disable the integration. For more information about disabling the integration, see Disable the Tanium Security Browser Connector for Microsoft Edge for Business integration on page 216.

> **Note:** Assign the **Asset API User** system role to your user account to revoke an API token. You can rotate an API token before expiration, which revokes the existing API token and generates a new API token. For more information, see Rotate the Tanium Security Browser Connector for Microsoft Edge for Business API token on page 214.

1. In a browser window, go to Tanium Console and sign in.
2. From the Main menu, go to **Shared Services** > **Integrations Gallery** and then click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Go to the **Configuration** tab.
4. Click **Revoke**.
   The existing API token that is associated with this integration is revoked.

Disable the Tanium Security Browser Connector for Microsoft Edge for Business integration

About this task

To fully disable the Tanium Security Browser Connector for Microsoft Edge for Business integration, in Tanium Console, disable the integration. This also removes all Microsoft Edge for Business browser use and related data from Tanium, revokes the API token, and deletes the **Microsoft Edge for Business API User** system persona. Then, in the Microsoft 365 admin center, remove the Tanium reporting connector and delete the Microsoft Edge for Business configuration policy that you created for this integration.

1. In a browser window, go to Tanium Console and sign in.
2. From the Main menu, go to **Shared Services** > **Integrations Gallery** and then click **Tanium**

©2026 Tanium Inc. All Rights Reserved

Security Browser Connector for Microsoft Edge for Business.

3. Select the **Service Enablement** toggle to disable the integration.
4. In a separate browser window, go to the Microsoft 365 admin center and sign in.
5. From the Main menu, go to **Settings** > **Microsoft Edge**.
6. Click **Connectors**.
7. In the Tanium pane, click **Set up**.
8. Click **Remove** and confirm your selection.
9. Click **Configuration policies**.
10. Select the configuration policy that you created for this integration.
11. Click **Delete policy** and then confirm your selection.

Use Tanium Security Browser Connector for Microsoft Edge for Business data

Important: Due to how Microsoft Azure creates virtual machines, multiple virtual machines that run Windows 10 or later might be assigned non-unique device IDs. All virtual machines with the same non-unique device ID are recognized as a single virtual machine in Tanium Data Service. Microsoft Edge for Business browser data from multiple virtual machines might not appear properly in reports and dashboards. For more information about how to assign unique device IDs, see Cannot properly view browser use data from multiple endpoints on page 220.

View Tanium Security Browser Connector for Microsoft Edge for Business reports and dashboards

About this task

Important: To view Asset-related dashboard panels and reports, add **Microsoft Edge** as a tracked application in the Tanium Asset module. For more information, see Tanium Asset User Guide: Enable tracking in Asset.

©2026 Tanium Inc. All Rights Reserved

Important: To view Performance-related dashboard panels and reports, add **Microsoft Edge** as a monitored application in the Tanium Performance module. For more information, see Tanium Performance User Guide: Monitoring applications.

The Tanium Security Browser Connector for Microsoft Edge for Business provides Tanium-managed reports and dashboards that you can use to view Microsoft Edge for Business browser behavior. You can drill down into the report or dashboard data to gain more insight into possible malicious behavior from the report or dashboard.

Note: These dashboards show information only for endpoints that run Tanium Client and meet the requirements for the Tanium Security Browser Connector for Microsoft Edge for Business. If you configure an entity provider to ingest an entity that otherwise meets the requirements for the Tanium Security Browser Connector for Microsoft Edge for Business, and the entity does not have Tanium Client installed, browser data for this entity does not appear in the dashboards.

1. In a browser window, go to Tanium Console and sign in.
2. From the Main menu, go to **Shared Services** > **Integrations Gallery** and then click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **Tanium Content**.

Include Security Browser Connector data in a report

About this task

When you work in the **Explore Data** page or edit a report, the **Source Data** panel lists all registered sensors, along with certain sources of data that are not present on endpoints (for more information, see Tanium Reporting User Guide: Registered sensors). Use the panel to add data sources as columns to the grid in the page or report. Each column lists the results that endpoints returned for the corresponding sensor or lists the values that Tanium solutions calculated for other data sources. If a single source produces multiple columns of results, the column headings show the source name above the column names.

1. Perform one of the following steps based on whether you plan to edit an existing report or create a new view of endpoint data that you might or might not save as a report.
    - Existing report: Open the report and click **Edit Data**. For more information about opening a report, see Tanium Reporting User Guide: Working with Reporting reports.

©2026 Tanium Inc. All Rights Reserved

- New view or report: From the Main menu, go to **Data** > **Explore Data**.

  Tip: You can also access the **Explore Data** page from the following locations:

  - An existing report: Click **New Report** or, in a non-editable report, click **Explore Data**.
  - The **Data** > **Reports** page: Click **Create Report**.

2. Select a Data Source to limit the results to endpoints managed using Tanium Client or an entity provider, or select All Entities to return results from all endpoints.

   Note: Select Save as default to save your current Data Source selection for future reports.

3. Configure the report. For more information, see Tanium Reporting User Guide: Explore data and create reports.

   Note: If you select **Microsoft Intune** or **All Endpoints** as the **Data Source**, you can filter results to show only endpoints running the iOS or Android operating system.

Export Security Browser Connector data using Tanium Connect

If the connection source supports Microsoft Edge for Business browser data, such as the **Tanium Reporting (Source Data)** source, you can export this data using Tanium Connect. For more information, see Tanium Connect User Guide: Overview.

Troubleshooting

If the Tanium Security Browser Connector for Microsoft Edge for Business is not performing as expected, you might need to troubleshoot issues or change settings.

Collect logs

About this task

The information is saved as a ZIP file that you can download with your browser. The ZIP file is also

©2026 Tanium Inc. All Rights Reserved

known as a support bundle.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. In the **Integrations** section, click **Tanium Security Browser Connector for Microsoft Edge for Business**.
3. Click **Support**.
4. Click **Create Package**.
   Step result: An integrations-gallery-support-bundle.[timestamp].zip file downloads to the local download directory.
5. Contact Tanium Support to determine the best option to send the ZIP file. For more information, see View the Support page on page 208.

Cannot retrieve browser use data from Microsoft Edge for Business instances

If the Tanium Security Browser Connector for Microsoft Edge for Business cannot retrieve browser use data related to Microsoft Edge for Business, verify that the API token is still valid, that the **Microsoft Edge for Business API User** persona exists, and that the Tanium reporting connector configuration in the Microsoft 365 admin center has the correct URL, port (`443`), and API token value.

Cannot properly view browser use data from multiple endpoints

Each endpoint that sends Microsoft Edge for Business browser use metrics must have a unique device ID. Browser use metrics are correlated per device ID. If multiple devices have the same device ID, browser use metrics might not appear properly in reports and dashboards.

Due to how Microsoft Azure creates virtual machines, multiple virtual machines that run Windows 10 or later might be assigned non-unique device IDs. All virtual machines with the same non-unique device ID are recognized as a single virtual machine in Tanium Data Service.

Update the registry key for each virtual machine at HKLM\SOFTWARE\Microsoft\SQMClient\MachineId to assign a device ID that is unique across all monitored endpoints.

Important: Improperly updating the registry might cause the endpoint to stop operating. Create backups and plan updates before starting.

©2026 Tanium Inc. All Rights Reserved

Troubleshooting Integrations Gallery

If Integrations Gallery is not performing as expected, you might need to troubleshoot issues or change settings.

Collect Tanium Account logs

The information is saved as a ZIP file that you can download with your browser. The ZIP file is also known as a support bundle.

1. From the Main menu, go to **Shared Services** > **Integrations Gallery**.
2. Click Help ?.
3. Click **Download Support Bundle**.

   A tanium-Account Management-support-[timestamp].zip file downloads to the local download directory.
4. Contact Tanium Support to determine the best option to send the ZIP file. For more information, see Contact Tanium Support on page 221.

Contact Tanium Support

To contact Tanium Support for help, sign in to the Tanium Customer Community.

For more information about submitting a support case, see Case Submission Form.

©2026 Tanium Inc. All Rights Reserved